

Vivante Programming: DPU API reference guide

Note: This document is released as part of PSOC™-E84 Early Access Pack (EAP).

About this document

Scope and purpose

This document describes various Display Processor Unit (DPU) APIs available for the user to make use of Display Controller in PSOC™ Edge devices.

Intended audience

This document is intended for anyone who wants to make use of DPU API for performing Display Controller operations on PSOC™ Edge devices.

Table of contents

Table of contents

About this document.....	1
Table of contents.....	2
1 Overview.....	5
1.1 Compatibility.....	5
1.2 API files	5
2 Data structures	6
2.1 Value types	6
2.2 Pointer types	7
2.3 Enumerations	8
2.3.1 vivSTATUS	8
2.3.2 viv_input_format_type	8
2.3.3 viv_tiling_type.....	11
2.3.4 viv_display_type	12
2.3.5 viv_dbi_type	12
2.3.6 viv_display_trans_mode.....	12
2.3.7 viv_cmd_te_type.....	12
2.3.8 viv_display_format_type	13
2.3.9 viv_filter_tap_type.....	14
2.3.10 viv_write_back_type.....	15
2.3.11 viv_cursor_size_type	15
2.3.12 viv_alpha_mode.....	15
2.3.13 viv_cache_mode	15
2.3.14 viv_global_alpha_mode	15
2.3.15 viv_porter_duff_mode.....	16
2.3.16 viv_pool_type.....	17
2.3.17 viv_rotation_type.....	17
2.3.18 viv_display_size_type	17
2.3.19 viv_display.....	18
2.3.20 viv_lut_enlarge.....	18
2.3.21 viv_dc_features.....	19
2.3.22 viv_dc_layer_cap	19
2.3.23 viv_layer_status	20
2.3.24 viv_csc_mode.....	20
2.4 Structures	20
2.4.1 viv_dc_buffer.....	20
2.4.2 viv_tilestatus_buffer	21
2.4.3 viv_cursor	22
2.4.4 viv_layer_alpha_mode	23
2.4.5 viv_dc_degama.....	23
2.4.6 viv_dc_gamma	23
2.4.7 viv_output	23
2.4.8 viv_dc_rect.....	24
2.4.9 viv_dc_color	24
3 DPU APIs	25
3.1 Initialization.....	25
3.1.1 viv_dc_init().....	25
3.1.2 viv_dc_deinit().....	26

Table of contents

3.1.3	viv_dc_reset()	26
3.2	Buffer allocation	27
3.2.1	viv_alloc_buffer()	27
3.2.2	viv_free_buffer()	28
3.2.3	viv_map_buffer()	29
3.2.4	viv_unmap_buffer()	30
3.3	Capability query	31
3.3.1	viv_query_chipinfo()	31
3.3.2	viv_dc_query_feature()	32
3.3.3	viv_layer_query_capability()	33
3.4	Overlay and video/graphic layers	33
3.4.1	viv_dc_select_layer()	33
3.4.2	viv_layer_enable()	34
3.4.3	viv_layer_set()	35
3.4.4	viv_layer_security()	35
3.4.5	viv_layer_zorder()	36
3.4.6	viv_layer_set_position()	37
3.4.7	viv_layer_rotation()	38
3.4.8	viv_layer_decompress()	38
3.4.9	viv_layer_cache_mode()	39
3.4.10	viv_layer_colorkey()	40
3.4.11	viv_layer_clear()	41
3.4.12	viv_layer_roi_enable()	42
3.4.13	viv_layer_roi_rect()	43
3.4.14	viv_set_alpha()	43
3.4.15	viv_layer_potterduff_blend()	44
3.4.16	viv_layer_set_y2r()	45
3.4.17	viv_layer_degamma_enable()	46
3.4.18	viv_layer_degamma_init()	47
3.4.19	viv_layer_set_degamma()	48
3.4.20	viv_layer_set_r2r()	49
3.4.21	viv_layer_set_watermark()	50
3.4.22	viv_dc_set_qos()	50
3.4.23	viv_layer_set_display()	51
3.4.24	viv_layer_get_status()	51
3.4.25	viv_dc_request()	52
3.5	Background and cursor layers	53
3.5.1	viv_layer_set_background()	53
3.5.2	viv_set_color_bar()	54
3.5.3	viv_set_cursor()	55
3.5.4	viv_cursor_security()	56
3.5.5	viv_cursor_offset()	57
3.5.6	viv_cursor_move()	58
3.6	Post-processing for display	59
3.6.1	viv_gamma_enable()	59
3.6.2	viv_gamma_init()	60
3.6.3	viv_set_gamma()	61
3.6.4	viv_set_3d_lut()	62
3.6.5	viv_set_3d_lut_enlarge()	63
3.6.6	viv_set_output_csc()	64

Table of contents

3.6.7	viv_set_dither()	65
3.7	Display output	66
3.7.1	viv_set_display_size()	66
3.7.2	viv_set_custom_display_size().....	67
3.7.3	viv_set_output()	68
3.7.4	viv_reset_dbi().....	69
3.7.5	viv_set_output_dbi().....	69
3.8	Display controller access and debugging.....	70
3.8.1	viv_set_commit()	70
3.8.2	viv_get_vblank_count()	71
3.8.3	viv_set_dest()	71
3.8.4	viv_set_write_back_dither().....	73
4	Programming with DPU APIs	74
4.1	Example 1: Displaying through DPI	75
4.2	Example 2: Displaying through DBI Type B	77
	Revision history.....	79
	Disclaimer.....	80

1 Overview

1 Overview

The DPU API set serves to develop user applications to control Vivante display controllers of the newest architecture. For the supported display controllers, see Section [1.1, Compatibility](#).

This document describes the APIs and the data structures used in the DPU API set. It also outlines the procedure of programming with this API set.

- Chapter [2, Data structures](#)
- Chapter [3, DPU APIs](#)
- Chapter [4, Programming with DPU APIs](#)

1.1 Compatibility

This API set is compatible with the DC8000Nano Vivante display controller hardware used in PSOC™ Edge Platform.

1.2 API files

The definition files for data structures and APIs are:

- Types and enumerations:

viv_dc_type.h

- APIs:

viv_dc_setting.h

2 Data structures

2 Data structures

2.1 Value types

The following table lists the value types defined in the DPU API set.

Table 1 Value types

Name	Definition	Description
gctBOOL	int	A Boolean value <ul style="list-style-type: none"> 0: SET_DISABLE, SET_NEGATIVE, vivFALSE, or gcvFALSE 1: SET_ENABLE, SET_POSITIVE, vivTRUE, or gcvTRUE
gctCHAR	char	An 8-bit character value
gctFLOAT	float	A single-precision floating-point number
gctINT	int	A signed integer
gctINT8	signed char	A signed 8-bit integer
gctINT16	signed short	A signed 16-bit integer
gctINT32	signed int	A signed 32-bit integer
gctINT64	signed long long	A signed 64-bit integer
gctSIZE_T	unsigned long	An unsigned 64-bit integer
gctUINT	unsigned int	An unsigned integer
gctUINT8	unsigned char	An unsigned 8-bit integer
gctUINT16	unsigned short	An unsigned 16-bit integer
gctUINT32	unsigned int	An unsigned 32-bit integer
gctUINT64	unsigned long long	An unsigned 64-bit integer
gctVOID	void	Void
gctDOUBLE	double	A double-precision floating-point number

2 Data structures

2.2 Pointer types

The following table lists the pointer types defined in the DPU API set. For the referent data types, see Section 2.1, [Value types](#).

Table 2 Pointer types

Pointer type	Name	Description
<code>gctBOOL *</code>	<code>gctBOOL_PTR</code>	A pointer to a Boolean value
<code>void *</code>	<code>gctFILE</code>	A pointer to a file
<code>float *</code>	<code>gctFLOAT_PTR</code>	A pointer to a single-precision floating-point number
<code>void *</code>	<code>gctHANDLE</code>	A handle of the operating system
<code>gctINT *</code>	<code>gctINT_PTR</code>	A pointer to a signed integer
<code>gctINT8 *</code>	<code>gctINT8_PTR</code>	A pointer to a signed 8-bit integer
<code>gctINT16 *</code>	<code>gctINT16_PTR</code>	A pointer to a signed 16-bit integer
<code>gctINT32 *</code>	<code>gctINT32_PTR</code>	A pointer to a signed 32-bit integer
<code>gctINT64 *</code>	<code>gctINT64_PTR</code>	A pointer to a signed 64-bit integer
<code>void *</code>	<code>gctPHYS_ADDR</code>	A pointer to a physical address
<code>void *</code>	<code>gctPOINTER</code>	A generic pointer
<code>gctSIZE_T *</code>	<code>gctSIZE_T_PTR</code>	A pointer to an unsigned 64-bit integer
<code>void *</code>	<code>gctSTRING</code>	A pointer to a string
<code>gctUINT *</code>	<code>gctUINT_PTR</code>	A pointer to an unsigned integer
<code>gctUINT8 *</code>	<code>gctUINT8_PTR</code>	A pointer to an unsigned 8-bit integer
<code>gctUINT16 *</code>	<code>gctUINT16_PTR</code>	A pointer to an unsigned 16-bit integer
<code>gctUINT32 *</code>	<code>gctUINT32_PTR</code>	A pointer to an unsigned 32-bit integer
<code>gctUINT64 *</code>	<code>gctUINT64_PTR</code>	A pointer to an unsigned 64-bit integer

2 Data structures

2.3 Enumerations

2.3.1 vivSTATUS

Specifies the return code of a DPU API.

Enumeration value	Numeric value	Description
vivSTATUS_HEAP_CORRUPTED	-7	Heap corrupted
vivSTATUS_OUT_OF_RESOURCES	-6	Resource access out of bounds
vivSTATUS_TIMEOUT	-5	Timeout
vivSTATUS_NOT_SUPPORT	-4	Unsupported features
vivSTATUS_OOM	-3	Out of memory
vivSTATUS_FAILED	-2	File operation failed
vivSTATUS_INVALID_ARGUMENTS	-1	Invalid input parameters
vivSTATUS_OK	0	Function successful

2.3.2 viv_input_format_type

Specifies the color format of the input.

RGB formats

Note: Before using a 24 bpp RGB format, call [viv_layer_query_capability\(\)](#) with `vivLAYER_CAP_FORMAT_24BIT` to query whether the display controller supports 24 bpp RGB formats.

Enumeration value	Description
vivARGB4444	16-bit ARGB format with the alpha channel in bits 15:12, the red channel in bits 11:8, the green channel in bits 7:4, and the blue channel in bits 3:0
vivABGR4444	16-bit ABGR format with the alpha channel in bits 15:12, the blue channel in bits 11:8, the green channel in bits 7:4, and the red channel in bits 3:0
vivRGBA4444	16-bit RGBA format with the red channel in bits 15:12, the green channel in bits 11:8, the blue channel in bits 7:4, and the alpha channel in bits 3:0
vivBGRA4444	16-bit BGRA format with the blue channel in bits 15:12, the green channel in bits 11:8, the red channel in bits 7:4, and the alpha channel in bits 3:0
vivXRGB4444	16-bit XRGB format with the X channel in bits 15:12, the red channel in bits 11:8, the green channel in bits 7:4, and the blue channel in bits 3:0
vivXBGR4444	16-bit XBGR format with the X channel in bits 15:12, the blue channel in bits 11:8, the green channel in bits 7:4, and the red channel in bits 3:0
vivRGBX4444	16-bit RGBX format with the red channel in bits 15:12, the green channel in bits 11:8, the blue channel in bits 7:4, and the X channel in bits 3:0
vivBGRX4444	16-bit BGRX format with the blue channel in bits 15:12, the green channel in bits 11:8, the red channel in bits 7:4, and the X channel in bits 3:0
vivARGB1555	16-bit ARGB format with the alpha channel in bit 15, the red channel in bits 14:10, the green channel in bits 9:5, and the blue channel in bits 4:0

2 Data structures

Enumeration value	Description
vivABGR1555	16-bit ABGR format with the alpha channel in bit 15, the blue channel in bits 14:10, the green channel in bits 9:5, and the red channel in bits 4:0
vivRGBA1555	16-bit RGBA format with the red channel in bits 15:11, the green channel in bits 10:6, the blue channel in bits 5:1, and the alpha channel in bit 0
vivBGRA1555	16-bit BGRA format with the blue channel in bits 15:11, the green channel in bits 10:6, the red channel in bits 5:1, and the alpha channel in bit 0
vivXRGB1555	16-bit XRGB format with the X channel in bit 15, the red channel in bits 14:10, the green channel in bits 9:5, and the blue channel in bits 4:0
vivXBGR1555	16-bit XBGR format with the X channel in bit 15, the blue channel in bits 14:10, the green channel in bits 9:5, and the red channel in bits 4:0
vivRGBX1555	16-bit RGBX format with the red channel in bits 15:11, the green channel in bits 10:6, the blue channel in bits 5:1, and the X channel in bit 0
vivBGRX1555	16-bit BGRX format with the blue channel in bits 15:11, the green channel in bits 10:6, the red channel in bits 5:1, and the X channel in bit 0
vivRGB565	16-bit RGB format with the red channel in bits 15:11, the green channel in bits 10:5, and the blue channel in bits 4:0
vivBGR565	16-bit BGR format with the blue channel in bits 15:11, the green channel in bits 10:5, and the red channel in bits 4:0
vivARGB8565	24-bit ARGB format with the alpha channel in bits 23:16, the red channel in bits 15:11, the green channel in bits 10:5, and the blue channel in bits 4:0
vivABGR8565	24-bit ABGR format with the alpha channel in bits 23:16, the blue channel in bits 15:11, the green channel in bits 10:5, and the red channel in bits 4:0
vivRGBA5658	24-bit RGBA format with the red channel in bits 23:19, the green channel in bits 18:13, the blue channel in bits 12:8, and the alpha channel in bits 7:0
vivBGRA5658	24-bit BGRA format with the blue channel in bits 23:19, the green channel in bits 18:13, the red channel in bits 12:8, and the alpha channel in bits 7:0
vivRGB888	24-bit RGB format with the red channel in bits 23:16, the green channel in bits 15:8, and the blue channel in bits 7:0
vivBGR888	24-bit BGR format with the blue channel in bits 23:16, the green channel in bits 15:8, and the red channel in bits 7:0
vivARGB8888	32-bit ARGB format with the alpha channel in bits 31:24, the red channel in bits 23:16, the green channel in bits 15:8, and the blue channel in bits 7:0
vivABGR8888	32-bit ABGR format with the alpha channel in bits 31:24, the blue channel in bits 23:16, the green channel in bits 15:8, and the red channel in bits 7:0
vivRGBA8888	32-bit RGBA format with the red channel in bits 31:24, the green channel in bits 23:16, the blue channel in bits 15:8, and the alpha channel in bits 7:0
vivBGRA8888	32-bit BGRA format with the blue channel in bits 31:24, the green channel in bits 23:16, the red channel in bits 15:8, and the alpha channel in bits 7:0
vivXRGB8888	32-bit XRGB format with the X channel in bits 31:24, the red channel in bits 23:16, the green channel in bits 15:8, and the blue channel in bits 7:0
vivXBGR8888	32-bit XBGR format with the X channel in bits 31:24, the blue channel in bits 23:16, the green channel in bits 15:8, and the red channel in bits 7:0

2 Data structures

Enumeration value	Description
vivRGBX8888	32-bit RGBX format with the red channel in bits 31:24, the green channel in bits 23:16, the blue channel in bits 15:8, and the X channel in bits 7:0
vivBGRX8888	32-bit BGRX format with the blue channel in bits 31:24, the green channel in bits 23:16, the red channel in bits 15:8, and the X channel in bits 7:0
vivARGB2101010	32-bit ARGB2101010 format with the alpha channel in bits 31:30, the red channel in bits 29:20, the green channel in bits 19:10, and the blue channel in bits 9:0
vivCURSOR_ARGB	The ARGB8888 format, which is supported for the cursor. For details about this format, see the description of vivARGB8888 .

YUV formats

Enumeration value	Description
vivYUY2	Packed YUV422 format, 32 bits for 2 pixels, with Y0 in bits 31:24, U0 in bits 23:16, Y1 in bits 15:8, and V0 in bits 7:0.
vivUYVY	Packed YUV422 format, 32 bits for 2 pixels, with U0 in bits 31:24, Y0 in bits 23:16, V0 in bits 15:8, and Y1 in bits 7:0.
vivNV16	YUV422 semi-planar format with 8 bits occupied by the Y plane and 16 bits occupied by the UV plane per pixel.
vivNV12	YUV420 semi-planar format, also named NV12, with an 8-bit Y plane in one pixel placed before each 16-bit array of packed U (Cb) and V (Cr) planes. The stride of the V and U planes is the same as that of the Y plane, but a V or U plane contains half of the lines in a Y plane.
vivYV12	YUV420 planar format with 8 bits occupied by the Y plane, 8 bits occupied by the U plane, and 8 bits occupied by the V plane per pixel.
vivP010	YUV420 semi-planar format. The Y plane occupies 16 bits per pixel but uses only 10 bits. The UV plane occupies 32 bits per pixel but uses only 20 bits.
vivNV12_10BIT	YUV420 semi-planar format, also named NV12, with a 10-bit Y plane in one pixel placed before each 20-bit array of packed U (Cb) and V (Cr) planes. Four Y-plane pixels occupies 5 bytes. The stride of the V and U planes is the same as that of the Y plane, but a V or U plane contains half of the lines in a Y plane. Only special DC8200 IPs support this format.
vivYUV444	YUV444 planar format with 8 bits occupied by the Y plane, 8 bits occupied by the U plane, and 8 bits occupied by the V plane per pixel. Only special DC8200 IPs support this format.
vivYUV444_10BIT	YUV444 planar format with 10 bits occupied by the Y plane, 10 bits occupied by the U plane, and 10 bits occupied by the V plane per pixel. Four Y-plane pixels occupies 5 bytes. Only special DC8200 IPs support this format.

2 Data structures

2.3.3 viv_tiling_type

Specifies the tiling type.

Enumeration value	Description
vivLINEAR	Linear
vivTILED4X4 ¹	Tile 4x4
vivTILED8X8 ¹	Tile 8x8
vivSUPERTILEDX ¹	SupertileX 8x8 or 8x4
vivSUPERTILEDY ¹	SupertileY 4x8

- Valid only for layers that support tiling. To query whether the tiling feature is supported, call [viv_layer_query_capability\(\)](#) with vivLAYER_CAP_TILED.

The following table lists the tiling types supported for each input color format.

Note: Each RGB color format listed includes their variants with the same channel bitwidth and different channel orders.

Color format	Linear	Tile 4x4	Tile 8x8	SupertileX	SupertileY
vivARGB8888	Supported			8x4 Supported	Supported
vivXRGB8888	Supported			8x4 Supported	Supported
vivARGB2101010	Supported			8x4 Supported	Supported
vivRGB565	Supported			8x8 Supported	
vivARGB1555	Supported			8x8 Supported	
vivXRGB1555	Supported			8x8 Supported	
vivARGB4444	Supported			8x8 Supported	
vivXRGB4444	Supported			8x8 Supported	
vivYUY2	Supported		Supported		
vivUYVY	Supported		Supported		
vivNV12	Supported	Supported	Supported		
vivP010	Supported		Supported		
vivNV16	Supported				
vivYV12	Supported				
vivNV12_10BIT		Supported			
vivYUV444		Supported			
vivYUV444_10BIT		Supported			

2 Data structures

2.3.4 viv_display_type

Specifies the output interface type.

To query whether an output interface is supported, call [viv_dc_query_feature\(\)](#).

Enumeration value	Description
vivDPI	The Display Pixel Interface (DPI)
vivDP	The DisplayPort (DP)
vivEDP	Reserved
vivDBI	The Display Bus Interface (DBI)

2.3.5 viv_dbi_type

Specifies the type of the Display Bus Interface (DBI).

This enumeration is valid only for display controllers that support DBI output. To query whether DBI output is supported, call the [viv_dc_query_feature\(\)](#) API with vivFEATURE_DBI.

Enumeration value	Description
vivDBI_AFIXED	Type A Fixed E mode
vivDBI_ACLOCK	Type A Clocked E mode
vivDBI_B	Type B
vivDBI_C	Type C

2.3.6 viv_display_trans_mode

Specifies the display transmission mode.

Enumeration value	Description
vivDISPLAY_TRANS_MODE_VIDEO	Video mode
vivDISPLAY_TRANS_MODE_COMMAND	Command mode

2.3.7 viv_cmd_te_type

Specifies the trigger of the tearing effect (TE) signal in command mode.

Enumeration Value	Description
vivCMD_TE_FROM_HW	The TE signal is triggered by hardware.
vivCMD_TE_FROM_SW	The TE signal is triggered by software.

2 Data structures

2.3.8 viv_display_format_type

Specifies the color format of the display controller output.

DPI Output

The following table lists the color formats supported for DPI output.

Enumeration value	Description
vivD24	RGB888
vivD30	RGB101010
vivD16CFG1	RGB565, config 1
vivD16CFG2	RGB565, config 2
vivD16CFG3	RGB565, config 3
vivD18CFG1	RGB666, config 1
vivD18CFG2	RGB666, config 2

DP RGB output

The following table lists the color formats supported for DP RGB output.

Enumeration value	Description
vivDPRGB565	RGB565
vivDPRGB666	RGB666
vivDPRGB888	RGB888
vivDPRGB101010	RGB101010

DP YUV output

The following table lists the color formats supported for DP YUV output.

Enumeration value	Description
vivDPYUV420B8CFG1	8-bit YUV420, config 1
vivDPYUV420B8CFG2	8-bit YUV420, config 2
vivDPYUV420B8CFG3	8-bit YUV420, config 3
vivDPYUV422B8CFG1	8-bit YUV422, config 1
vivDPYUV422B8CFG2	8-bit YUV422, config 2
vivDPYUV444B8CFG1	8-bit YUV444, config 1
vivDPYUV444B8CFG2	8-bit YUV444, config 2
vivDPYUV444B8CFG3	8-bit YUV444, config 3
vivDPYUV420B10CFG1	10-bit YUV420, config 1
vivDPYUV420B10CFG2	10-bit YUV420, config 2
vivDPYUV420B10CFG3	10-bit YUV420, config 3
vivDPYUV422B10CFG1	10-bit YUV422, config 1
vivDPYUV422B10CFG2	10-bit YUV422, config 2

2 Data structures

Enumeration value	Description
vivDPYUV444B10CFG1	10-bit YUV444, config 1
vivDPYUV444B10CFG2	10-bit YUV444, config 2
vivDPYUV444B10CFG3	10-bit YUV444, config 3

DBI output

The following table lists the color formats supported for DBI output. To query whether DBI output is supported, call [viv_dc_query_feature\(\)](#) with vivFEATURE_DBI.

Enumeration value	Description
vivD8R3G3B2	D8R3G3B2 for DBI type A and type B
vivD8B2G3R3	D8B2G3R3 for DBI type B
vivD8R4G4B4	D8R4G4B4 for DBI type A and type B
vivD8R5G6B5	D8R5G6B5 for DBI type A and type B
vivD8R6G6B6	D8R6G6B6 for DBI type A and type B
vivD8R8G8B8	D8R8G8B8 for DBI type A and type B
vivD9R6G6B6	D9R6G6B6 for DBI type A and type B
vivD16R3G3B2	D16R3G3B2 for DBI type A and type B
vivD16R4G4B4	D16R4G4B4 for DBI type A and type B
vivD16R5G6B5	D16R5G6B5 for DBI type A and type B
vivD16R6G6B6OP1	D16R6G6B6 option 1 for DBI type A and type B
vivD16R6G6B6OP2	D16R6G6B6 option 2 for DBI type A and type B
vivD16R8G8B8OP1	D16R8G8B8 option 1 for DBI type A and type B
vivD16R8G8B8OP2	D16R8G8B8 option 2 for DBI type A and type B
vivD1R5G6B5OP1	D1R5G6B5 option 1 for DBI type C
vivD1R5G6B5OP2	D1R5G6B5 option 2 for DBI type C
vivD1R5G6B5OP3	D1R5G6B5 option 3 for DBI type C
vivD1R8G8B8OP1	D1R8G8B8 option 1 for DBI type C
vivD1R8G8B8OP2	D1R8G8B8 option 2 for DBI type C
vivD1R8G8B8OP3	D1R8G8B8 option 3 for DBI type C

2.3.9 viv_filter_tap_type

Specifies the filter tap type.

In the following table, filter tap patterns are described in [horizontal tap count] x [vertical tap count] format.

Enumeration value	Description
vivFILTER_H3_V3	The filter with 3 x 3 taps
vivFILTER_H5_V3	The filter with 5 x 3 taps

2 Data structures

2.3.10 viv_write_back_type

Specifies the location inside the display controller to write back data.

This enumeration is valid only for display controllers that support the write-back feature. To query whether write-back is supported, call [viv_dc_query_feature\(\)](#) with vivFEATURE_WRITEBACK.

Enumeration value	Description
vivWB_DEFAULT	Sends the output of the last module before display output to a specified buffer.

2.3.11 viv_cursor_size_type

Specifies the cursor size.

Enumeration value	Description
vivCURSOR_32x32	32 x 32 pixels.
vivCURSOR_64x64	64 x 64 pixels. This value is valid only if the cursor version is 1. To query the cursor version, call viv_dc_query_feature() with vivFEATURE_CURSOR_VERSION.

2.3.12 viv_alpha_mode

Specifies whether to reverse the alpha value.

Enumeration value	Description
vivALPHA_NORMAL	Does not reverse the alpha value.
vivALPHA_INVERSED	Reverses the alpha value.

2.3.13 viv_cache_mode

Specifies the cache mode.

Enumeration value	Description
vivCACHE_NONE	No cache configured
vivCACHE_128	128 bytes
vivCACHE_256	256 bytes

2.3.14 viv_global_alpha_mode

Specifies the type of the alpha value.

Enumeration value	Description
vivGALPHA_NORMAL	Pixel alpha values are used.
vivGALPHA_GLOBAL	The global alpha value is used.
vivGALPHA_SCALED	The used alpha value is scaled from pixel alpha values and the global alpha value.

2 Data structures

2.3.15 viv_porter_duff_mode

Specifies the Porter-Duff blend mode.

In the following table, Sa indicates the source alpha value, Da indicates the destination alpha value, Sc indicates the source color value, and Dc indicates the destination color value.

Enumeration value	Description
vivPD_CLEAR	Clears destination pixels covered by the source to 0. <ul style="list-style-type: none"> Result alpha value = 0 Result color value = 0
vivPD_SRC	Replaces the destination pixels with the source pixels. <ul style="list-style-type: none"> Result alpha value = Sa Result color value = Sc
vivPD_DST	Discards the source pixels and leaves the destination unchanged. <ul style="list-style-type: none"> Result alpha value = Da Result color value = Dc
vivPD_SRC_OVER	Draws the source pixels over the destination pixels. <ul style="list-style-type: none"> Result alpha value = $Sa + (1 - Sa) \times Da$ Result color value = $Sc + (1 - Sa) \times Dc$
vivPD_DST_OVER	Draws the source pixels behind the destination pixels. <ul style="list-style-type: none"> Result alpha value = $Da + (1 - Da) \times Sa$ Result color value = $Dc + (1 - Da) \times Sc$
vivPD_SRC_IN	Keeps the source pixels that cover the destination pixels, and discards the remaining source and destination pixels. <ul style="list-style-type: none"> Result alpha value = $Sa \times Da$ Result color value = $Sc \times Da$
vivPD_DST_IN	Keeps the destination pixels that cover source pixels, and discards the remaining source and destination pixels. <ul style="list-style-type: none"> Result alpha value = $Sa \times Da$ Result color value = $Sa \times Dc$
vivPD_SRC_OUT	Keeps the source pixels that do not cover destination pixels, and discards the remaining source and destination pixels. <ul style="list-style-type: none"> Result alpha value = $Sa \times (1 - Da)$ Result color value = $Sc \times (1 - Da)$
vivPD_DST_OUT	Keeps the destination pixels that are not covered by source pixels, and discards the remaining source and destination pixels. <ul style="list-style-type: none"> Result alpha value = $Da \times (1 - Sa)$ Result color value = $Dc \times (1 - Sa)$
vivPD_SRC_ATOP	Discards the source pixels that do not cover destination pixels, and draws the remaining source pixels over destination pixels. <ul style="list-style-type: none"> Result alpha value = Da Result color value = $Sc \times Da + (1 - Sa) \times Dc$

2 Data structures

Enumeration value	Description
vivPD_DST_ATOP	Discards the destination pixels that are not covered by source pixels, and draws the remaining destination pixels over source pixels. <ul style="list-style-type: none"> Result alpha value = S_a Result color value = $S_a \times D_c + S_c \times (1 - D_a)$
vivPD_XOR	Discards the source and destination pixels where source pixels cover destination pixels, and draws the remaining source pixels. <ul style="list-style-type: none"> Result alpha value = $S_a + D_a - 2 \times S_a \times D_a$ Result color value = $S_c \times (1 - D_a) + (1 - S_a) \times D_c$

2.3.16 viv_pool_type

Specifies the memory allocation strategy.

Enumeration Value	Description
gcvPOOL_CONTIGUOUS	Allocates contiguous memory. If no contiguous memory is available, the allocation fails.
gcvPOOL_DEFAULT	Tries to allocate contiguous memory. If no contiguous memory is available, the system allocates memory with discrete pages.
gcvPOOL_USER	Uses user-reserved memory.

2.3.17 viv_rotation_type

Specifies the rotation or flipping method.

Before rotating or flipping a layer, call [viv_layer_query_capability\(\)](#) with vivLAYER_CAP_ROTATION or vivLAYER_CAP_FLIP to query whether the layer supports the feature.

Enumeration value	Description
vivROTANGLE_0	Does not rotate or flip.
vivROTANGLE_90	Rotates 90° in anticlockwise direction.
vivROTANGLE_180	Rotates 180° in anticlockwise direction.
vivROTANGLE_270	Rotates 270° in anticlockwise direction.
vivROTANGLE_FLIPX	Flips along the X axis.
vivROTANGLE_FLIPY	Flips along the Y axis.
vivROTANGLE_FLIPXY	Flips along the X axis and the Y axis.

2.3.18 viv_display_size_type

Specifies the display resolution and refresh rate.

Enumeration value	Description
vivDISPLAY_320_480_60	320 x 480 resolution at a refresh rate of 60 Hz
vivDISPLAY_480_800_60	480 x 800 resolution at a refresh rate of 60 Hz
vivDISPLAY_480_864_60	480 x 864 resolution at a refresh rate of 60 Hz
vivDISPLAY_640_480_60	640 x 480 resolution at a refresh rate of 60 Hz

2 Data structures

Enumeration value	Description
vivDISPLAY_720_480_60	720 x 480 resolution at a refresh rate of 60 Hz
vivDISPLAY_800_480_60	800 x 480 resolution at a refresh rate of 60 Hz
vivDISPLAY_1024_600_60	1024 x 600 resolution at a refresh rate of 60 Hz
vivDISPLAY_1024_768_60	1024 x 768 resolution at a refresh rate of 60 Hz
vivDISPLAY_1280_720_60	1280 x 720 resolution at a refresh rate of 60 Hz
vivDISPLAY_1920_1080_60	1920 x 1080 resolution at a refresh rate of 60 Hz
vivDISPLAY_3840_2160_30	3840 x 2160 resolution at a refresh rate of 30 Hz
vivDISPLAY_3840_2160_60	3840 x 2160 resolution at a refresh rate of 60 Hz
vivDISPLAY_4096_2160_60	4096 x 2160 resolution at a refresh rate of 60 Hz
vivDISPLAY_5760_756_60	5760 x 756 resolution at a refresh rate of 60 Hz
vivDISPLAY_CUSTOMIZED	Custom resolution

2.3.19 viv_display

Specifies the display panel.

Enumeration value	Description
vivDISPLAY_0	The display0 panel
vivDISPLAY_1	The display1 panel

2.3.20 viv_lut_enlarge

Specifies the enlarge mode of color channel values.

This enumeration is valid only for display controllers that support the 3D LUT feature. To query whether 3D LUT is supported, call [viv_dc_query_feature\(\)](#) with vivFEATURE_3D_LUT.

Enumeration value	Description
vivLUT_ENLARGE0	Does not enlarge the color channel values.
vivLUT_ENLARGE9	Enlarges each color channel value by 2^n , where: <ul style="list-style-type: none"> $n = 9$ – Bitwidth of the greatest value among the red, green, and blue channels
vivLUT_ENLARGE10	Enlarges each color channel value by 2^n , where: <ul style="list-style-type: none"> $n = 10$ – Bitwidth of the greatest value among the red, green, and blue channels

2 Data structures

2.3.21 viv_dc_features

Specifies the feature for [viv_dc_query_feature\(\)](#) to query.

Enumeration value	Description
vivFEATURE_DISPLAY_COUNT	The number of supported panels
vivFEATURE_LAYER_COUNT	The total number of supported overlay layers and video/graphic layers
vivFEATURE_CURSOR_COUNT	The number of supported cursor layers
vivFEATURE_GAMMA_BIT_OUT	The number of output bits of the display gamma module
vivFEATURE_SECURITY	The secure mode, Trusted Execution Environment (TEE)
vivFEATURE_MMU	The memory management unit (MMU)
vivFEATURE_CURSOR_VERSION	The cursor version <ul style="list-style-type: none"> The value 0 indicates that only the cursor size 32 x 32 in pixels is supported. The value 1 indicates that the cursor sizes 32 x 32 and 64 x 64 in pixels are supported.
vivFEATURE_CSC_MOUDLE	The programmable color space conversion (CSC) matrix
vivFEATURE_3D_LUT	The 3D lookup table (LUT) feature
vivFEATURE_DE_GAMMA	The degamma feature
vivFEATURE_DP	Display Port feature
vivFEATURE_DP_YUV	Display Port with YUV feature
vivFEATURE_DBI	The Display Bus Interface (DBI) output
vivFEATURE_DPI	The Display Parallel Interface (DPI) output
vivFEATURE_NEW_GAMMA	The new gamma feature
vivFEATURE_COLOR_BAR	The color bar
vivFEATURE_CRC	The cyclic redundancy check (CRC) feature
vivFEATURE_40BIT_ADDRESS	The 40-bit address space
vivFEATURE_WRITEBACK	The write-back feature
vivFEATURE_PROGRAM_WB	Program Write Back buffer
vivFEATURE_CUSTOMER_TILE4X4	Custom tile alignment
vivFEATURE_DUAL_OS	The dual-OS feature.

2.3.22 viv_dc_layer_cap

Specifies the feature for [viv_layer_query_capability\(\)](#) to query.

Enumeration Value	Description
vivLAYER_CAP_DEC400_DECOMPRESSION	The DEC400 decompression feature
vivLAYER_CAP_SCALE	The filtering feature for scaling and sharpness
vivLAYER_CAP_TILED	The tiling feature
vivLAYER_CAP_ROTATION	The full rotation feature
vivLAYER_CAP_ROI	The region of interest (ROI) feature

2 Data structures

2.3.23 viv_layer_status

Specifies the layer status.

This enumeration is valid only for display controllers that support dual OSes. To query whether the dual OS feature is supported, call [viv_dc_query_feature\(\)](#) with `vivFEATURE_DUAL_OS`.

Enumeration value	Description
<code>vivLAYER_IDLE</code>	The layer is idle.
<code>vivLAYER_OCCUPIED_BY_SELF</code>	The layer is occupied by its associated OS.
<code>vivLAYER_OCCUPIED_BY_OTHERS</code>	The layer is occupied by the OS other than the layer associated OS.

2.3.24 viv_csc_mode

Specifies the color space conversion (CSC) mode.

Enumeration value	Description
<code>vivCSC_BT601</code>	BT.601, a standard color conversion mode.
<code>vivCSC_BT709</code>	BT.709, a standard color conversion mode.
<code>vivCSC_BT2020</code>	BT.2020, a standard color conversion mode.
<code>vivCSC_USER_DEF</code>	A customized mode with user-defined CSC matrix coefficients.

2.4 Structures

2.4.1 viv_dc_buffer

The structure to configure the buffer for a layer to access.

Member	Type	Description
<code>handle[3]</code>	gctPOINTER	(Optional) The handle of the buffer memory, obtained from the viv_alloc_buffer() API.
<code>logical[3]</code>	gctPOINTER	(Optional) A pointer to the CPU logical address of the buffer, obtained from the viv_alloc_buffer() API.
<code>phyAddress[3]</code>	gctUINT64	The physical addresses of the buffer.
<code>gpuAddress[3]</code>	gctUINT64	(Optional) The DPU virtual addresses of the buffer, obtained from the viv_map_buffer() or viv_alloc_buffer() API. This member is valid only for display controllers with MMU. To query the support for MMU, call viv_dc_query_feature() with <code>vivFEATURE_MMU</code> .
<code>format</code>	viv_input_format_type	The color format of the layer input. This parameter is valid only for overlay layers and video/graphic layers. For cursor layers, use the format member in the viv_cursor structure instead.
<code>security</code>	gctBOOL	(Optional) Specifies whether to enable the secure mode for the buffer. The available values include: <ul style="list-style-type: none"> <code>vivTRUE</code>: Enables the secure mode. <code>vivFALSE</code>: Disables the secure mode.

2 Data structures

Member	Type	Description
		Set this member to the same value as the security parameter in the viv_map_buffer() or viv_alloc_buffer() API. This member is valid only if the display controller is configured with MMU and supports the secure mode. To query the support for the secure mode and MMU, call viv_dc_query_feature() with <code>vivFEATURE_SECURITY</code> and <code>vivFEATURE_MMU</code> separately.
pool	viv_pool_type	(Optional) The memory allocation strategy. Set this member to the same value as the Pool parameter in the viv_map_buffer() or viv_alloc_buffer() API.
tiling	viv_tiling_type	The tiling type of the layer input.
width	gctUINT32	The width of the layer input.
height	gctUINT32	The height of the layer input.
stride[3]	gctUINT32	The stride of each plane.

See also

[3.2.1 viv_alloc_buffer\(\)](#)

[3.2.3 viv_map_buffer\(\)](#)

[3.3.2 viv_dc_query_feature\(\)](#)

[3.4.3 viv_layer_set\(\)](#)

[3.5.3 viv_set_cursor\(\)](#)

[3.8.3 viv_set_dest\(\)](#)

2.4.2 viv_tilestatus_buffer

The structure to configure the tile status buffer for a layer.

Member	Type	Description
tileStatusHandle[3]	gctPOINTER	(Optional) The handle of the buffer memory, obtained from the viv_alloc_buffer() API.
tileStatusLogical[3]	gctPOINTER	(Optional) A pointer to the CPU logical address of the buffer, obtained from the viv_alloc_buffer() API.
tileStatusHWAddress[3]	gctUINT64	The physical addresses of the buffer.
tileStatusGPUAddress[3]	gctUINT64	(Optional) The DPU virtual addresses of the buffer, obtained from the viv_map_buffer() or viv_alloc_buffer() API. This member is valid only for display controllers with MMU. To query the support for MMU, call viv_dc_query_feature() with <code>vivFEATURE_MMU</code> .
format	viv_input_format_type	(Optional) The color format of the layer input.
security	gctBOOL	(Optional) Specifies whether to enable the secure mode for the buffer. The available values include: <ul style="list-style-type: none"> <code>vivTRUE</code>: Enables the secure mode.

2 Data structures

Member	Type	Description
		<ul style="list-style-type: none"> <code>vivFALSE</code>: Disables the secure mode. <p>Set this member to the same value as the security parameter in the <code>viv_map_buffer()</code> or <code>viv_alloc_buffer()</code> API.</p> <p>This member is valid only if the display controller is configured with MMU and supports the secure mode. To query the support for the secure mode and MMU, call <code>viv_dc_query_feature()</code> with <code>vivFEATURE_SECURITY</code> and <code>vivFEATURE_MMU</code> separately.</p>
<code>pool</code>	<code>viv_pool_type</code>	(Optional) The memory allocation strategy. Set this member to the same value as the Pool parameter in the <code>viv_map_buffer()</code> or <code>viv_alloc_buffer()</code> API.
<code>tiling</code>	<code>viv_tiling_type</code>	(Optional) The tiling type of the layer input.
<code>width</code>	<code>gctUINT32</code>	(Optional) The width of the layer input.
<code>height</code>	<code>gctUINT32</code>	(Optional) The height of the layer input.

See also

[3.2.1 viv_alloc_buffer\(\)](#)

[3.4.8 viv_layer_decompress\(\)](#)

2.4.3 viv_cursor

The structure of a cursor.

Member	Type	Description
<code>hsx</code>	<code>gctUINT32</code>	The X offset, in pixels, of the top-left point to the hotspot.
<code>hsy</code>	<code>gctUINT32</code>	The Y offset, in pixels, of the top-left point to the hotspot.
<code>x</code>	<code>gctUINT32</code>	The X coordinate, in pixels, of the hotspot.
<code>y</code>	<code>gctUINT32</code>	The Y coordinate, in pixels, of the hotspot.
<code>size</code>	<code>viv_write_back_type</code>	The size of the cursor.
<code>bg_color</code>	<code>gctUINT</code>	The background color in the specified format.
<code>fg_color</code>	<code>gctUINT</code>	The foreground color in the specified format.
<code>format</code>	<code>viv_input_format_type</code>	<p>The input color format of the cursor.</p> <p>Set this parameter to <code>vivCURSOR_ARGB</code> or leave it unspecified.</p>

2 Data structures

2.4.4 viv_layer_alpha_mode

The structure of the alpha value configurations.

Member	Type	Description
srcGlobalAlphaMode	viv_global_alpha_mode	The type of the alpha value to use for the source.
srcGlobalAlphaValue	gctUINT32	The global alpha value for the source.
srcAlphaMode	viv_alpha_mode	Specifies whether to reverse the source alpha value.
srcAlphaValue	gctUINT32	Reserved.
dstGlobalAlphaMode	viv_global_alpha_mode	The type of the alpha value to use for the destination.
dstGlobalAlphaValue	gctUINT32	The global alpha value for the destination.
dstAlphaMode	viv_alpha_mode	Specifies whether to reverse the destination alpha value.
dstAlphaValue	gctUINT32	Reserved.

2.4.5 viv_dc_degamma

The structure of a degamma table.

Member	Type	Description
degammaTable[260][3]	gctUINT16	The degamma table with a size of 260 rows and 3 columns <ul style="list-style-type: none"> degammaTable[index][0]: The value for the red channel degammaTable[index][1]: The value for the green channel degammaTable[index][2]: The value for the blue channel where, <i>index</i> is a value in the range of [0, 259].

2.4.6 viv_dc_gamma

The structure of a gamma table.

Member	Type	Description
gammaTable[300][3]	gctUINT16	The gamma table with a size of 300 rows and 3 columns <ul style="list-style-type: none"> gammaTable[index][0]: The value for the red channel gammaTable[index][1]: The value for the green channel gammaTable[index][2]: The value for the blue channel where <i>index</i> is a value in the range of [0, 299].

2.4.7 viv_output

Specifies the output interface type, color format and DPI related attributes.

Member	Type	Description
type	viv_display_type	The output interface type
format	viv_display_format_type	The output color format

2 Data structures

2.4.8 viv_dc_rect

The structure of a rectangle.

Member	Type	Description
x	gctUINT32	The X coordinate, in pixels, of the rectangle top-left point
y	gctUINT32	The Y coordinate, in pixels, of the rectangle top-left point
w	gctUINT32	The width, in pixels, of the rectangle
h	gctUINT32	The height, in pixels, of the rectangle

2.4.9 viv_dc_color

The structure of an RGB color.

Member	Type	Description
a	gctUINT8	The value of the alpha channel
r	gctUINT8	The value of the red channel
g	gctUINT8	The value of the green channel
b	gctUINT8	The value of the blue channel

3 DPU APIs

3 DPU APIs

3.1 Initialization

This section describes the APIs for display controller initialization, de-initialization, and reset.

3.1.1 `viv_dc_init()`

Description

Starts the display controller and initializes platform-related functions.

Call this API before using the display controller hardware. Do not repeatedly call this API before `viv_dc_deinit()` is called.

Syntax

```
vivSTATUS viv_dc_init(  
    gctVOID  
);
```

Parameters

None.

Returns

`vivSTATUS`

See also

[3.1.2 `viv_dc_deinit\(\)`](#)

3 DPU APIs

3.1.2 viv_dc_deinit()

Description

Terminates the platform-related functions and stops the display controller.

Call this API after the application completes. After this API is executed, call `viv_dc_init()` before any other DPU API.

Syntax

```
vivSTATUS viv_dc_deinit(  
    gctVOID  
);
```

Parameters

None.

Returns

`vivSTATUS`

See also

[3.1.1 viv_dc_init\(\)](#)

3.1.3 viv_dc_reset()

Description

Resets the display controller.

Syntax

```
vivSTATUS viv_dc_reset(  
    gctVOID  
);
```

Parameters

None.

Returns

`vivSTATUS`

3 DPU APIs

3.2 Buffer allocation

This section describes the APIs for buffer management.

3.2.1 viv_alloc_buffer()

Description

Allocates system memory to a buffer.

Syntax

```
vivSTATUS viv_alloc_buffer(
    gctUINT32 Size,
    gctPOINTER *Handle,
    gctUINT32 *HardwareAddress,
    gctPOINTER *Logical,
    gctBOOL security,
    viv_pool_type Pool
);
```

Parameters

Parameter	Data type	Description
Size	gctUINT32	The memory size, in bytes, to allocate. For viv_dc_buffer: <ul style="list-style-type: none"> If the input data is in RGB format, the required memory size is: $\text{height} \times \text{width} \times \text{Number of bytes per pixel (Bpp)}$ If the input data is in YUV format, the required memory size is the sum of the result of the above formula for each plane. For viv_tilestatus_buffer, the recommended memory size is: Memory size of viv_dc_buffer/128
Handle	gctPOINTER *	An output parameter that serves as the handle of the allocated memory.
HardwareAddress	gctUINT32 *	An output parameter that indicates the physical address of the memory buffer.
Logical	gctPOINTER *	An output parameter that indicates the current CPU logical address of the memory buffer.
security	gctBOOL	Specifies whether to enable the secure mode for the memory buffer. Set this parameter to one of the following values: <ul style="list-style-type: none"> vivTRUE: Enables the secure mode. If the secure mode is enabled for the buffer, enable the secure mode for the layer with viv_cursor_security() or viv_layer_security() to ensure successful access from the layer to the buffer. vivFALSE: Disables the secure mode. This parameter is valid only if the display controller is configured with MMU and supports the secure mode. To query the support for the

3 DPU APIs

Parameter	Data type	Description
		secure mode and MMU, call <code>viv_dc_query_feature()</code> with <code>vivFEATURE_SECURITY</code> and <code>vivFEATURE_MMU</code> separately.
Pool	viv_pool_type	The memory allocation strategy. Set this parameter to <code>gcvPOOL_CONTIGUOUS</code> or <code>gcvPOOL_DEFAULT</code> . The value must be the same as that you set in the <code>viv_dc_buffer</code> or <code>viv_tilestatus_buffer</code> object.

Returns

[vivSTATUS](#)

See also

[2.4.1 viv_dc_buffer](#)

[2.4.2 viv_tilestatus_buffer](#)

[3.2.2 viv_free_buffer\(\)](#)

[3.2.3 viv_map_buffer\(\)](#)

[3.3.2 viv_dc_query_feature\(\)](#)

[3.4.4 viv_layer_security\(\)](#)

[3.5.4 viv_cursor_security\(\)](#)

3.2.2 viv_free_buffer()

Description

Frees the buffer memory allocated with `viv_alloc_buffer()`.

Syntax

```
vivSTATUS viv_free_buffer(
    gctPOINTER handle
);
```

Parameters

Parameter	Data type	Description
handle	gctPOINTER	The handle of the buffer memory to free.

Returns

[vivSTATUS](#)

See also

[3.2.1 viv_alloc_buffer\(\)](#)

3 DPU APIs

3.2.3 viv_map_buffer()

Description

Maps user-reserved memory to DPU virtual addresses.

This API is valid only for display controllers with MMU. Before using this API, call `viv_dc_query_feature()` with `vivFEATURE_MMU` to check whether the MMU is supported.

Syntax

```
vivSTATUS viv_map_buffer(
    gctUINT size,
    gctUINT64 physicalAddr,
    gctUINT *dcVirtualAddr,
    gctBOOL security,
    viv_pool_type pool
);
```

Parameters

Parameter	Data type	Description
size	gctUINT	The memory size, in bytes, to map.
physicalAddr	gctUINT64	The physical address, which must not exceed 40 bits.
dcVirtualAddr	gctUINT *	An output parameter that indicates the DPU virtual address, which must not exceed 32 bits.
security	gctBOOL	Specifies whether to enable the secure mode for the memory. Set this parameter to one of the following values: <ul style="list-style-type: none"> <code>vivTRUE</code>: Enables the secure mode. If the secure mode is enabled for the buffer, enable the secure mode for the layer with <code>viv_cursor_security()</code> or <code>viv_layer_security()</code> to ensure successful access from the layer to the buffer. <code>vivFALSE</code>: Disables the secure mode. This parameter is valid only if the display controller is configured with MMU and supports the secure mode. To query the support for the secure mode and MMU, call <code>viv_dc_query_feature()</code> with <code>vivFEATURE_SECURITY</code> and <code>vivFEATURE_MMU</code> separately.
pool	viv_pool_type	The memory allocation strategy. Set this parameter to <code>gcvPOOL_USER</code> . The value must be the same as that you set in the <code>viv_dc_buffer</code> or <code>viv_tilestatus_buffer</code> object.

Returns

[vivSTATUS](#)

3 DPU APIs

See also

[2.4.1 viv_dc_buffer](#)

[2.4.2 viv_tilestatus_buffer](#)

[3.2.1 viv_alloc_buffer\(\)](#)

[3.2.4 viv_unmap_buffer\(\)](#)

[3.3.2 viv_dc_query_feature\(\)](#)

[3.4.4 viv_layer_security\(\)](#)

[3.5.4 viv_cursor_security\(\)](#)

3.2.4 viv_unmap_buffer()

Description

Cancels the mapping between user-reserved memory and DPU virtual addresses.

This API is valid only for display controllers with MMU. Before using this API, call `viv_dc_query_feature()` with `vivFEATURE_MMU` to check whether the MMU is supported.

Syntax

```
vivSTATUS viv_unmap_buffer(  
    gctUINT size,  
    gctUINT dcVirtualAddr  
);
```

Parameters

Parameter	Data type	Description
size	gctUINT	The size, in bytes, of the memory to unmap.
dcVirtualAddr	gctUINT	The DPU virtual address, which must not exceed 32 bits.

Returns

[vivSTATUS](#)

See also

[3.3.2 viv_dc_query_feature\(\)](#)

[3.2.3 viv_map_buffer\(\)](#)

3 DPU APIs

3.3 Capability query

This section describes the APIs you can use to query the feature support of the display controller and each layer.

3.3.1 `viv_query_chipinfo()`

Description

Queries the list of features that the display controller supports. The order of the listed features follows that in the `viv_dc_features` structure, where the first feature is `vivFEATURE_DISPLAY_COUNT`.

Syntax

```
vivSTATUS viv_query_chipinfo (  
    gctBOOL *Features  
);
```

Parameters

Parameter	Data type	Description
Features	gctBOOL *	A pointer to the feature list.

Returns

[vivSTATUS](#)

See also

[2.3.21 viv_dc_features](#)

[3.3.2 viv_dc_query_feature\(\)](#)

3 DPU APIs

3.3.2 viv_dc_query_feature()

Description

Queries whether the display controller supports a specified feature. Before you call this API, use the `viv_query_chipinfo()` API to obtain the list of supported features.

To query the write-back support, use this API with `vivFEATURE_WRITEBACK` and the `viv_display_query_capability()` API with `vivDISPLAY_CAP_PROGRAM_WB` separately.

Syntax

```
vivSTATUS viv_dc_query_feature(
    viv_dc_features feature
    gctUINT* value
);
```

Parameters

Parameter	Data type	Description
feature	viv_dc_features	The feature to query.
value	gctUINT *	<p>The return value.</p> <ul style="list-style-type: none"> If the queried feature is <code>vivFEATURE_DISPLAY_COUNT</code>, <code>vivFEATURE_LAYER_COUNT</code>, or <code>vivFEATURE_CURSOR_COUNT</code>, the return value indicates the number of panels or layers. If the queried feature is <code>vivFEATURE_CURSOR_VERSION</code>: <ul style="list-style-type: none"> The value 1 indicates that the cursor sizes 32 x 32 and 64 x 64 in pixels are supported. The value 0 indicates that only the cursor size 32 x 32 in pixels is supported. For other features: <ul style="list-style-type: none"> The value 1 indicates that the queried feature is supported. The value 0 indicates that the queried feature is not supported.

Returns

[vivSTATUS](#)

See also

[3.3.1 viv_query_chipinfo\(\)](#)

3 DPU APIs

3.3.3 viv_layer_query_capability()

Description

Queries whether a layer supports a specified feature.

Syntax

```
vivSTATUS viv_layer_query_capability(
    gctUINT layer_id,
    viv_dc_layer_cap cap
    gctUINT* value
);
```

Parameters

Parameter	Data type	Description
layer_id	gctUINT	The ID of the layer to query. For the ID of each layer, see Section 3.4.1, viv_dc_select_layer() .
Cap	viv_dc_layer_cap	The feature to query.
value	gctUINT *	The return value. The possible values include: <ul style="list-style-type: none"> vivTRUE: The queried feature is supported. vivFALSE: The queried feature is not supported.

Returns

[vivSTATUS](#)

3.4 Overlay and video/graphic layers

This section describes the APIs you can use to configure the overlay and video/graphic layers. For the support of overlay and video/graphic layers by each display controller, see Section 3.4.1, [viv_dc_select_layer\(\)](#).

3.4.1 viv_dc_select_layer()

Description

Selects an overlay or video/graphic layer by ID. The ID of each layer for different display controller hardware revisions is listed in the following table.

Hardware revision	Software-hardware layer mapping
DC8200 revisions excluding 5_7_2_rc0x	Software: {0, 1, 2, 3, 4, 5} Hardware: {video0, overlay0, overlay1, video1, overlay2, overlay3}
DC8200 5_7_2_rc0x	Software: {0, 1, 2, 3} Hardware: {video0, overlay0, video1, overlay2}
DC8000Nano 5_5_4_rc3d	Software: {0, 1, 2} Hardware: {video0, overlay0, overlay1}

Before configuring an overlay or video/graphic layer, call this API to switch to the layer.

3 DPU APIs

Syntax

```
vivSTATUS viv_dc_select_layer (  
    gctUINT  layerId  
);
```

Parameters

Parameter	Data type	Description
layerId	gctUINT	The ID of the layer to select.

Returns

[vivSTATUS](#)

3.4.2 viv_layer_enable()

Description

Enables or disables the selected overlay or video/graphic layer.

Syntax

```
vivSTATUS viv_layer_enable (  
    gctBOOL enable  
);
```

Parameters

Parameter	Data type	Description
Enable	gctBOOL	Specifies whether to enable the layer. Set this parameter to one of the following values: <ul style="list-style-type: none">vivTRUE: Enables the layer.vivFALSE: Disables the layer.

Returns

[vivSTATUS](#)

See also

[3.4.1 viv_dc_select_layer\(\)](#)

3 DPU APIs

3.4.3 viv_layer_set()

Description

Assigns a buffer to the selected overlay or video/graphic layer.

Before you call this API, make sure that the buffer memory is available. To use system memory, call `viv_alloc_buffer()` for memory allocation.

Syntax

```
vivSTATUS viv_layer_set(
    viv_dc_buffer *buffer
);
```

Parameters

Parameter	Data type	Description
buffer	viv_dc_buffer *	A pointer to the buffer.

Returns

[vivSTATUS](#)

See also

[3.2.1 viv_alloc_buffer\(\)](#)

[3.4.1 viv_dc_select_layer\(\)](#)

[3.4.2 viv_layer_enable\(\)](#)

3.4.4 viv_layer_security()

Description

Enables or disables the secure mode for the selected overlay or video/graphic layer.

This API is valid only for display controllers that support the secure mode. Before using this API, call `viv_dc_query_feature()` with `vivFEATURE_SECURITY` to check whether the secure mode is supported.

Syntax

```
vivSTATUS viv_layer_security(
    gctBOOL layer_sec
);
```

Parameters

Parameter	Data type	Description
layer_sec	gctBOOL	Specifies whether to enable the secure mode for the layer. Set this parameter to one of the following values: <ul style="list-style-type: none"> <code>vivTRUE</code>: Enables the secure mode. <code>vivFALSE</code>: Disables the secure mode.

3 DPU APIs

Returns

[vivSTATUS](#)

See also

[3.3.2 viv_dc_query_feature\(\)](#)

[3.4.1 viv_dc_select_layer\(\)](#)

[3.4.2 viv_layer_enable\(\)](#)

3.4.5 viv_layer_zorder()

Description

Configures the z-order for the selected overly or video/graphic layer in a blending or color keying operation. For the blending and color keying description, see Vivante hardware features document specific to the DPU hardware version.

Syntax

```
vivSTATUS viv_layer_zorder(  
    gctUINT8 zorder  
);
```

Parameters

Parameter	Data type	Description
zorder	gctUINT8	<p>The z-order of the layer.</p> <p>The value 0 indicates the bottom layer sitting above the background layer. Other numbers index the ordering of the front layers.</p> <p>The default background color is RGB(0, 0, 0). To change the background color, use the viv_layer_set_background() API.</p>

Returns

[vivSTATUS](#)

See also

[3.4.1 viv_dc_select_layer\(\)](#)

[3.4.2 viv_layer_enable\(\)](#)

[3.5.1 viv_layer_set_background\(\)](#)

3 DPU APIs

3.4.6 viv_layer_set_position()

Description

Sets the start coordinates for the selected overlay or video/graphic layer to display on a panel.

Syntax

```
vivSTATUS viv_layer_set_position(  
    gctUINT    x,  
    gctUINT    y  
);
```

Parameters

Parameter	Data type	Description
x	gctUINT	The X coordinate of the start point for the layer.
y	gctUINT	The Y coordinate of the start point for the layer.

Returns

[vivSTATUS](#)

See also

[3.4.1 viv_dc_select_layer\(\)](#)

[3.4.2 viv_layer_enable\(\)](#)

3 DPU APIs

3.4.7 viv_layer_rotation()

Description

Rotates or flips the selected overlay or video/graphic layer.

This API is valid only for layers that support the rotation and flip features. Before using this API, call `viv_layer_query_capability()` with `vivLAYER_CAP_ROTATION` or `vivLAYER_CAP_FLIP` to check whether the selected layer supports rotation or flip.

Syntax

```
vivSTATUS viv_layer_rotation(
    viv_rotation_type rotation
);
```

Parameters

Parameter	Data type	Description
rotation	viv_rotation_type	The rotation or flipping method.

Returns

[vivSTATUS](#)

See also

[3.3.3 viv_layer_query_capability\(\)](#)

[3.4.1 viv_dc_select_layer\(\)](#)

[3.4.2 viv_layer_enable\(\)](#)

3.4.8 viv_layer_decompress()

Description

Enables or disables DEC400 decompression for the selected overlay or video/graphic layer.

Before you call this API, make sure that a tile status buffer is configured. If you want the buffer to use system memory, call `viv_alloc_buffer()` for memory allocation.

This API is valid only for display controllers that support DEC400 decompression. Before using this API, call `viv_layer_query_capability()` with `vivLAYER_CAP_DEC400_DECOMPRESSION` to check whether DEC400 decompression is supported.

Syntax

```
vivSTATUS viv_layer_decompress(
    viv_tilestatus_buffer *tilebuffer,
    gctBOOL enable
);
```

3 DPU APIs

Parameters

Parameter	Data type	Description
tilebuffer	viv_tilestatus_buffer *	A pointer to the tile status buffer of the layer.
enable	gctBOOL	Specifies whether to enable DEC400 decompression for the layer. Set this parameter to one of the following values: <ul style="list-style-type: none">vivTRUE: Enables DEC400 decompression.vivFALSE: Disables DEC400 decompression.

Returns

[vivSTATUS](#)

See also

[3.2.1 viv_alloc_buffer\(\)](#)

[3.3.3 viv_layer_query_capability\(\)](#)

[3.4.1 viv_dc_select_layer\(\)](#)

[3.4.2 viv_layer_enable\(\)](#)

[3.4.9 viv_layer_cache_mode\(\)](#)

3.4.9 viv_layer_cache_mode()

Description

Sets the decompression cache mode for the selected overlay or video/graphic layer.

This API is valid only for layers that support DEC400 decompression. Before using this API, call [viv_layer_query_capability\(\)](#) with [vivLAYER_CAP_DEC400_DECOMPRESSION](#) to check whether the selected layer supports DEC400 decompression.

Syntax

```
vivSTATUS viv_layer_cache_mode(  
    viv_cache_mode cache_mode  
);
```

Parameters

Parameter	Data type	Description
cache_mode	viv_cache_mode	The decompression cache mode of the layer.

Returns

[vivSTATUS](#)

See also

[3.3.3 viv_layer_query_capability\(\)](#)

[3.4.1 viv_dc_select_layer\(\)](#)

3 DPU APIs

[3.4.2 viv_layer_enable\(\)](#)

[3.4.8 viv_layer_decompress\(\)](#)

3.4.10 viv_layer_colorkey()

Description

Configures the color keying feature for the selected overlay or video/graphic layer.

Syntax

```
vivSTATUS viv_layer_colorkey(  
    viv_dc_color *colorkey,  
    viv_dc_color *colorkeyHigh,  
    gctBOOL transparency  
);
```

Parameters

Parameter	Data type	Description
colorkey	viv_dc_color *	A pointer to the low color value of the range to key out.
colorkeyHigh	viv_dc_color *	A pointer to the high color value of the range to key out.
transparency	gctBOOL	Specifies whether to enable transparency of the matching range at the layer. Set this parameter to one of the following values: <ul style="list-style-type: none">vivTRUE: Enables the transparency.vivFALSE: Disables the transparency.

Returns

[vivSTATUS](#)

See also

[3.4.1 viv_dc_select_layer\(\)](#)

[3.4.2 viv_layer_enable\(\)](#)

3 DPU APIs

3.4.11 viv_layer_clear()

Description

Configures the clear feature for the selected overlay or video/graphic layer.

If the clear feature is enabled for the layer, the system takes the clear color as the source data of the layer and does not read data from the buffer of the layer.

If the layer clear feature is disabled and the DEC400 fast clear feature is enabled, the clear color is used as the DEC400 fast clear color. The system determines whether DEC400 fast clear is enabled based on the compression information in the buffer specified with the viv_layer_decompress() API.

Syntax

```
vivSTATUS viv_layer_clear(
    viv_dc_color *clearColor,
    gctBOOL enable
);
```

Parameters

Parameter	Data type	Description
clearColor	viv_dc_color *	A pointer to the clear color.
enable	gctBOOL	Specifies whether to enable the clear feature for the layer. Set this parameter to one of the following values: <ul style="list-style-type: none"> vivTRUE: Enables the clear feature. vivFALSE: Disables the clear feature.

Returns

[vivSTATUS](#)

See also

[3.4.1 viv_dc_select_layer\(\)](#)

[3.4.2 viv_layer_enable\(\)](#)

[3.4.8 viv_layer_decompress\(\)](#)

3 DPU APIs

3.4.12 viv_layer_roi_enable()

Description

Enables or disables region of interest (ROI) for the selected overlay or video/graphic layer.

This API is valid only for layers that support the ROI feature. Before using this API, call `viv_layer_query_capability()` with `vivLAYER_CAP_ROI` to check whether the selected layer supports ROI.

Syntax

```
vivSTATUS viv_layer_roi_enable(  
    gctBOOL enable  
);
```

Parameters

Parameter	Data type	Description
enable	gctBOOL	Specifies whether to enable the ROI feature for the layer. Set this parameter to one of the following values: <ul style="list-style-type: none"><code>vivTRUE</code>: Enables ROI.<code>vivFALSE</code>: Disables ROI.

Returns

[vivSTATUS](#)

See also

[3.3.3 viv_layer_query_capability\(\)](#)

[3.4.1 viv_dc_select_layer\(\)](#)

[3.4.2 viv_layer_enable\(\)](#)

[3.4.13 viv_layer_roi_rect\(\)](#)

3 DPU APIs

3.4.13 viv_layer_roi_rect()

Description

Configures the ROI in the buffer for the selected overlay or video/graphic layer.

This API is valid only for layers that support the ROI feature. Before using this API, call `viv_layer_query_capability()` with `vivLAYER_CAP_ROI` to check whether the selected layer supports ROI.

Syntax

```
vivSTATUS viv_layer_roi_rect(
    viv_dc_rect *rect
);
```

Parameters

Parameter	Data type	Description
rect	viv_dc_rect *	The ROI of the layer.

Returns

[vivSTATUS](#)

See also

[3.3.3 viv_layer_query_capability\(\)](#)

[3.4.1 viv_dc_select_layer\(\)](#)

[3.4.2 viv_layer_enable\(\)](#)

[3.4.12 viv_layer_roi_enable\(\)](#)

3.4.14 viv_set_alpha()

Description

Configures the source and destination alpha values for the selected overlay or video/graphic layer.

Syntax

```
vivSTATUS viv_set_alpha(
    viv_layer_alpha_mode *Alpha
);
```

Parameters

Parameter	Data type	Description
Alpha	viv_layer_alpha_mode *	A pointer to the alpha value configurations of the layer.

3 DPU APIs

Returns

[vivSTATUS](#)

See also

[3.4.1 viv_dc_select_layer\(\)](#)

[3.4.2 viv_layer_enable\(\)](#)

[3.4.15 viv_layer_poterduff_blend\(\)](#)

3.4.15 viv_layer_poterduff_blend()

Description

Enables or disables alpha blending for the selected overlay or video/graphic layer.

Syntax

```
vivSTATUS viv_layer_poterduff_blend(  
    gctBOOL    enable,  
    viv_porter_duff_mode Mode  
);
```

Parameters

Parameter	Data type	Description
Enable	gctBOOL	Specifies whether to enable alpha blending. Set this parameter to one of the following values: <ul style="list-style-type: none">vivTRUE: Enables alpha blending.vivFALSE: Disables alpha blending.
Mode	viv_porter_duff_mode	The Porter-Duff blend mode.

Returns

[vivSTATUS](#)

See also

[3.4.1 viv_dc_select_layer\(\)](#)

[3.4.2 viv_layer_enable\(\)](#)

[3.4.14 viv_set_alpha\(\)](#)

3 DPU APIs

3.4.16 viv_layer_set_y2r()

Description

Configures YUV-to-RGB color space conversion for the selected overlay or video/graphic layer.

Syntax

```
vivSTATUS viv_layer_set_y2r (  
    gctBOOL yuvClamp,  
    viv_csc_mode mode,  
    gctINT* coef,  
    gctUINT num  
);
```

Parameters

Parameter	Data type	Description
yuvClamp	gctBOOL	Specifies whether to enable YUV clamp.
mode	viv_csc_mode	The color space conversion (CSC) mode.
coef	gctINT *	A pointer to the CSC matrix coefficients. Set this parameter if mode is set to vivCSC_USER_DEF.
num	gctUINT	The number of CSC matrix coefficients in the array.

Returns

[vivSTATUS](#)

See also

[3.4.1 viv_dc_select_layer\(\)](#)

[3.4.2 viv_layer_enable\(\)](#)

3 DPU APIs

3.4.17 viv_layer_degama_enable()

Description

Enables or disables degamma for the selected overlay or video/graphic layer.

This API is valid only for display controllers that support degamma. Before using this API, call `viv_dc_query_feature()` with `vivFEATURE_DE_GAMMA` to check whether degamma is supported.

Syntax

```
vivSTATUS viv_layer_degama_enable(  
    gctBOOL    enable  
);
```

Parameters

Parameter	Data type	Description
enable	gctBOOL	Specifies whether to enable the degamma feature. Set this parameter to one of the following values: <ul style="list-style-type: none"><code>vivTRUE</code>: Enables degamma.<code>vivFALSE</code>: Disables degamma.

Returns

[vivSTATUS](#)

See also

[3.3.2 viv_dc_query_feature\(\)](#)

[3.4.1 viv_dc_select_layer\(\)](#)

[3.4.2 viv_layer_enable\(\)](#)

[3.4.18 viv_layer_degama_init\(\)](#)

[3.4.19 viv_layer_set_degama\(\)](#)

3 DPU APIs

3.4.18 viv_layer_degama_init()

Description

Initializes a degamma table for the selected overlay or video/graphic layer.

This API is valid only for display controllers that support degamma. Before using this API, call `viv_dc_query_feature()` with `vivFEATURE_DE_GAMMA` to check whether degamma is supported.

Syntax

```
vivSTATUS viv_layer_degama_init(  
    viv_dc_degama  *degama  
);
```

Parameters

Parameter	Data type	Description
degama	viv_dc_degama *	A pointer to the degamma table.

Returns

[vivSTATUS](#)

See also

[3.3.2 viv_dc_query_feature\(\)](#)

[3.4.1 viv_dc_select_layer\(\)](#)

[3.4.2 viv_layer_enable\(\)](#)

[3.4.17 viv_layer_degama_enable\(\)](#)

[3.4.19 viv_layer_set_degama\(\)](#)

3 DPU APIs

3.4.19 viv_layer_set_degama()

Description

Sets a row in the degamma table of the selected overlay or video/graphic layer.

Before you use this API, make sure that the degamma table of the layer is available. To initiate a degamma table, use the viv_layer_degama_init() API.

This API is valid only for display controllers that support degamma. Before using this API, call viv_dc_query_feature() with vivFEATURE_DE_GAMMA to check whether degamma is supported.

Syntax

```
vivSTATUS viv_layer_set_degama (
    gctUINT32    index,
    gctUINT16    r,
    gctUINT16    g,
    gctUINT16    b
);
```

Parameters

Parameter	Data type	Description
index	gctUINT32	The index of the row in the degamma table.
r	gctUINT16	The value for the red channel.
g	gctUINT16	The value for the green channel.
b	gctUINT16	The value for the blue channel.

Returns

[vivSTATUS](#)

See also

[3.3.2 viv_dc_query_feature\(\)](#)

[3.4.1 viv_dc_select_layer\(\)](#)

[3.4.2 viv_layer_enable\(\)](#)

[3.4.17 viv_layer_degama_enable\(\)](#)

[3.4.18 viv_layer_degama_init\(\)](#)

3 DPU APIs

3.4.20 viv_layer_set_r2r()

Description

Configures RGB-to-RGB color space conversion for the selected overlay or video/graphic layer.

Syntax

```
vivSTATUS viv_layer_set_r2r (  
    gctBOOL enable,  
    viv_csc_mode mode,  
    gctINT* coef,  
    gctUINT num  
);
```

Parameters

Parameter	Data type	Description
enable	gctBOOL	Specifies whether to enable RGB-to-RGB conversion.
mode	viv_csc_mode	The color space conversion (CSC) mode.
coef	gctINT *	A pointer to the CSC matrix coefficients. Set this parameter if mode is set to vivCSC_USER_DEF.
num	gctUINT	The number of CSC matrix coefficients in the array.

Returns

[vivSTATUS](#)

See also

[3.4.1 viv_dc_select_layer\(\)](#)

[3.4.2 viv_layer_enable\(\)](#)

3 DPU APIs

3.4.21 viv_layer_set_watermark()

Description

Sets the watermark value for the selected overlay or video/graphic layer.

Syntax

```
vivSTATUS viv_layer_set_watermark(  
    gctUINT32    watermark  
);
```

Parameters

Parameter	Data type	Description
watermark	gctUINT32	The watermark value.

Returns

[vivSTATUS](#)

See also

[3.4.1 viv_dc_select_layer\(\)](#)

[3.4.2 viv_layer_enable\(\)](#)

[3.4.22 viv_dc_set_qos\(\)](#)

3.4.22 viv_dc_set_qos()

Description

Sets the DPU QoS values for all overlay layers and video/graphic layers.

Syntax

```
vivSTATUS viv_dc_set_qos(  
    gctUINT32    low,  
    gctUINT32    high  
);
```

Parameters

Parameter	Data type	Description
low	gctUINT32	The QoS low value.
high	gctUINT32	The QoS high value.

Returns

[vivSTATUS](#)

See also

[3.4.21 viv_layer_set_watermark\(\)](#)

3 DPU APIs

3.4.23 viv_layer_set_display()

Description

Selects the display panel for the selected overlay or video/graphic layer.

Syntax

```
vivSTATUS viv_layer_set_display(  
    viv_display    display  
);
```

Parameters

Parameter	Data type	Description
display	viv_display	The ID of the display panel.

Returns

[vivSTATUS](#)

See also

[3.4.1 viv_dc_select_layer\(\)](#)

[3.4.2 viv_layer_enable\(\)](#)

3.4.24 viv_layer_get_status()

Description

Queries the status of the selected overlay or video/graphic layer.

This API is valid only for display controllers that support dual OSes. Before using this API, call `viv_dc_query_feature()` with `vivFEATURE_DUAL_OS` to check whether the dual OS feature is supported.

Syntax

```
vivSTATUS viv_layer_get_status(  
    viv_layer_status* status  
);
```

Parameters

Parameter	Data type	Description
status	viv_layer_status *	The pointer that receives the status of the selected layer.

Returns

[vivSTATUS](#)

See also

[3.3.2 viv_dc_query_feature\(\)](#)

[3.4.1 viv_dc_select_layer\(\)](#)

3 DPU APIs

[3.4.2 viv_layer_enable\(\)](#)

[3.4.25 viv_dc_request\(\)](#)

3.4.25 viv_dc_request()

Description

Sends an arbitration request to get the current OS prioritized for all overlay layers and video/graphic layers, and returns the arbitration result.

This API is valid only for display controllers that support dual OSes. Before using this API, call `viv_dc_query_feature()` with `vivFEATURE_DUAL_OS` to check whether the dual OS feature is supported.

Syntax

```
vivSTATUS viv_dc_request(  
    gctBOOL* success  
);
```

Parameters

Parameter	Data type	Description
Success	gctBOOL *	The pointer to receive the arbitration result.

Returns

[vivSTATUS](#)

See also

[3.3.2 viv_dc_query_feature\(\)](#)

[3.4.24 viv_layer_get_status\(\)](#)

3 DPU APIs

3.5 Background and cursor layers

This section describes the APIs you can use to configure background layers and cursor layers.

DC8200 supports two background layers and two cursor layers. Other display controllers support only one background layer and one cursor layer.

3.5.1 `viv_layer_set_background()`

Description

Sets the background color for a display panel. The panel shows the background color in a region only if the color bar is disabled for the region.

Syntax

```
vivSTATUS viv_layer_set_background(  
    viv_display    display,  
    viv_dc_color   *bgColor  
);
```

Parameters

Parameter	Data type	Description
display	viv_display	The ID of the display panel.
bgColor	viv_dc_color *	A pointer to the background color, which is default to RGB(0,0,0).

Returns

[vivSTATUS](#)

See also

[3.5.2 `viv_set_color_bar\(\)`](#)

3 DPU APIs

3.5.2 viv_set_color_bar()

Description

Configures the color bar for a display panel. If the color bar is enabled for a range, the panel shows the color bar instead of the background layer in the range. A maximum of 16 color bar ranges are supported.

This API is valid only for display controllers that support the color bar. Before using this API, call `viv_dc_query_feature()` with `vivFEATURE_COLOR_BAR` to check whether the color bar is supported.

Syntax

```
vivSTATUS viv_set_color_bar(
    viv_display display,
    gctBOOL enable,
    gctUINT index,
    viv_dc_rect *range,
    viv_dc_color *color
);
```

Parameters

Parameter	Data type	Description
display	viv_display	The ID of the display panel.
enable	gctBOOL	Specifies whether to enable the color bar for the range. Set this parameter to one of the following values: <ul style="list-style-type: none"> <code>vivTRUE</code>: Enables the color bar. <code>vivFALSE</code>: Disables the color bar.
index	gctINT	The index of the color bar range. Set this parameter to a value in the range from 0 to 15.
range	viv_dc_rect *	The region of the color bar range to display on the panel.
color	viv_dc_color *	The color of the color bar range.

Returns

[vivSTATUS](#)

See also

[3.3.2 viv_dc_query_feature\(\)](#)

[3.5.1 viv_layer_set_background\(\)](#)

3 DPU APIs

3.5.3 viv_set_cursor()

Description

Enables or disables the cursor layer for a display panel.

Before you call this API, make sure that a `viv_dc_buffer` object is configured for the layer. If you want the buffer to use system memory, call `viv_alloc_buffer()` for memory allocation.

Syntax

```
vivSTATUS viv_set_cursor(  
    viv_display display,  
    viv_dc_buffer *buffer,  
    viv_cursor *cursor,  
    gctBOOL enable  
);
```

Parameters

Parameter	Data type	Description
display	viv_display	The ID of the display panel whose cursor layer you want to configure. <i>Note: The cursor of the display0 panel is cursor0. The cursor of the display1 panel is cursor1.</i>
buffer	viv_dc_buffer *	A pointer to the buffer of the cursor layer.
cursor	viv_cursor *	A pointer to the cursor.
enable	gctBOOL	Specifies whether to enable the cursor layer. Set this parameter to one of the following values: <ul style="list-style-type: none"><code>vivTRUE</code>: Enables the cursor layer.<code>vivFALSE</code>: Disables the cursor layer.

Returns

[vivSTATUS](#)

See also

[3.2.1 viv_alloc_buffer\(\)](#)

[3.5.4 viv_cursor_security\(\)](#)

[3.5.5 viv_cursor_offset\(\)](#)

[3.5.6 viv_cursor_move\(\)](#)

3 DPU APIs

3.5.4 viv_cursor_security()

Description

Enables or disables the cursor layer in secure mode for a display panel.

This API is valid only for DC8200 that supports the secure mode. Before using this API, call `viv_dc_query_feature()` with `vivFEATURE_SECURITY` to check whether the secure mode is supported.

Note: Calling this API overwrites the setting of the enable parameter in [viv_set_cursor\(\)](#).

Syntax

```
vivSTATUS viv_cursor_security(  
    viv_display display,  
    gctBOOL enable  
);
```

Parameters

Parameter	Data type	Description
display	viv_display	The ID of the display panel whose cursor layer you want to configure. <i>Note:</i> The cursor of the display0 panel is cursor0. The cursor of the display1 panel is cursor1.
enable	gctBOOL	Specifies whether to enable the cursor layer. Set this parameter to one of the following values: <ul style="list-style-type: none"><code>vivTRUE</code>: Enables the cursor layer.<code>vivFALSE</code>: Disables the cursor layer.

Returns

[vivSTATUS](#)

See also

[3.3.2 viv_dc_query_feature\(\)](#)

[3.5.3 viv_set_cursor\(\)](#)

3 DPU APIs

3.5.5 viv_cursor_offset()

Description

Sets the offset of the cursor top-left point to the hotspot. The top-left point refers to the upper-left corner of the cursor bounding box.

Make sure that the hotspot be located within the cursor image. To query the supported cursor sizes, call `viv_dc_query_feature()` with `vivFEATURE_CURSOR_VERSION`.

Syntax

```
vivSTATUS viv_cursor_hotspot(
    viv_display display,
    gctUINT32 hsx,
    gctUINT32 hsy
);
```

Parameters

Parameter	Data type	Description
display	viv_display	The ID of the display panel whose cursor layer you want to configure. <i>Note: The cursor of the display0 panel is cursor0. The cursor of the display1 panel is cursor1.</i>
hsx	gctUINT32	The X offset, in pixels, of the top-left point to the hotspot.
hsy	gctUINT32	The Y offset, in pixels, of the top-left point to the hotspot.

Returns

[vivSTATUS](#)

See also

[3.3.2 viv_dc_query_feature\(\)](#)

[3.5.3 viv_set_cursor\(\)](#)

3 DPU APIs

3.5.6 viv_cursor_move()

Description

Sets a new position for the cursor hotspot on the same display panel.

Syntax

```
vivSTATUS viv_cursor_move(  
    viv_display display,  
    gctUINT32 x,  
    gctUINT32 y  
);
```

Parameters

Parameter	Data type	Description
display	viv_display	The ID of the display panel whose cursor layer you want to configure. <i>Note: The cursor of the display0 panel is cursor0. The cursor of the display1 panel is cursor1.</i>
x	gctUINT32	The new position X coordinate, in pixels, of the cursor hotspot.
y	gctUINT32	The new position Y coordinate, in pixels, of the cursor hotspot.

Returns

[vivSTATUS](#)

See also

[3.5.3 viv_set_cursor\(\)](#)

3 DPU APIs

3.6 Post-processing for display

This section describes the APIs for post-processing configurations.

3.6.1 `viv_gamma_enable()`

Description

Enables or disables the gamma feature for a display panel.

Syntax

```
vivSTATUS viv_gamma_enable(  
    viv_display display,  
    gctBOOL    enable  
);
```

Parameters

Parameter	Data type	Description
Display	viv_display	The ID of the display panel.
enable	gctBOOL	Specifies whether to enable the gamma feature. Set this parameter to one of the following values: <ul style="list-style-type: none"><code>vivTRUE</code>: Enables the feature.<code>vivFALSE</code>: Disables the feature.

Returns

[vivSTATUS](#)

See also

[3.6.2 `viv_gamma_init\(\)`](#)

[3.6.3 `viv_set_gamma\(\)`](#)

3 DPU APIs

3.6.2 viv_gamma_init()

Description

Initializes the gamma table.

Syntax

```
vivSTATUS viv_gamma_init(  
    viv_dc_gamma *gamma,  
    gctFLOAT gamma_value,  
    viv_dc_curve_type curve_type  
);
```

Parameters

Parameter	Data type	Description
Gamma	viv_dc_gamma *	A pointer to the gamma table.
gamma_value	gctFLOAT	The index of the gamma function. This parameter is valid only if curve_type is set to VIV_DC_CURVE_GAMMA.

Returns

[vivSTATUS](#)

See also

[3.6.1 viv_gamma_enable\(\)](#)

[3.6.3 viv_set_gamma\(\)](#)

3 DPU APIs

3.6.3 viv_set_gamma()

Description

Sets a row in a gamma table for a display panel.

Before you use this API, make sure that the table of the gamma feature is available. To initiate the table, use the `viv_gamma_init()` API.

Syntax

```
vivSTATUS viv_set_gamma(  
    viv_display display,  
    gctUINT32 index,  
    gctUINT16 r,  
    gctUINT16 g,  
    gctUINT16 b  
);
```

Parameters

Parameter	Data type	Description
display	viv_display	The ID of the display panel.
index	gctUINT32	The index of the row in the gamma table.
r	gctUINT16	The gamma correction value for the red channel.
g	gctUINT16	The gamma correction value for the green channel.
b	gctUINT16	The gamma correction value for the blue channel.

Returns

[vivSTATUS](#)

See also

[3.6.1 viv_gamma_enable\(\)](#)

[3.6.2 viv_gamma_init\(\)](#)

3 DPU APIs

3.6.4 viv_set_3d_lut()

Description

Enables or disables 3D lookup table (LUT) for a display panel.

This API is valid only for display controllers that support 3D LUT. Before using this API, call `viv_dc_query_feature()` with `vivFEATURE_3D_LUT` to check whether 3D LUT is supported.

Syntax

```
vivSTATUS viv_set_3d_lut(  
    viv_display display,  
    gctBOOL enable,  
    gctUINT32* threed_lut  
);
```

Parameters

Parameter	Data type	Description
display	viv_display	The ID of the display panel.
enable	gctBOOL	Specifies whether to enable the 3D LUT feature. Set this parameter to one of the following values: <ul style="list-style-type: none"><code>vivTRUE</code>: Enables 3D LUT.<code>vivFALSE</code>: Disables 3D LUT.
threed_lut	gctUINT32 *	A pointer to the 3D LUT with a size of 17 x 17 x 17.

Returns

[vivSTATUS](#)

See also

[3.3.2 viv_dc_query_feature\(\)](#)

[3.6.5 viv_set_3d_lut_enlarge\(\)](#)

3 DPU APIs

3.6.5 viv_set_3d_lut_enlarge()

Description

Configures the enlarge mode of color channel values for 3D LUT.

This API is valid only for display controllers that support 3D LUT. Before using this API, call `viv_dc_query_feature()` with `vivFEATURE_3D_LUT` to check whether 3D LUT is supported.

Syntax

```
vivSTATUS viv_set_3d_lut_enlarge(  
    viv_display display,  
    viv_lut_enlarge enlarge  
);
```

Parameters

Parameter	Data type	Description
Display	viv_display	The ID of the display panel.
enlarge	viv_lut_enlarge	The enlarge mode of color channel values.

Returns

[vivSTATUS](#)

See also

[3.3.2 viv_dc_query_feature\(\)](#)

[3.6.4 viv_set_3d_lut\(\)](#)

3 DPU APIs

3.6.6 viv_set_output_csc()

Description

Configures RGB-to-YUV conversion for the output to a display panel.

This API is valid only for display controllers that support the programmable color space conversion (CSC) matrix. Before using this API, call `viv_dc_query_feature()` with `vivFEATURE_CSC_MOUDLE` to check whether the CSC matrix is programmable.

Syntax

```
vivSTATUS viv_set_output_csc(
    viv_display display,
    gctBOOL fullRange,
    viv_csc_mode mode,
    gctINT *coef,
    gctUINT num,
);
```

Parameters

Parameter	Data type	Description
display	viv_display	The ID of the display panel.
fullRange	gctBOOL	Specifies whether to clamp the Y, U, and V values during RGB-to-YUV conversion. Set this parameter to one of the following values: <ul style="list-style-type: none"> <code>vivTRUE</code>: Clamps the Y, U, and V values. <code>vivFALSE</code>: Does not clamp the Y, U, or V value.
mode	viv_csc_mode	The color space conversion (CSC) mode.
coef	gctINT *	A pointer to the CSC matrix coefficients. Set this parameter if mode is set to <code>vivCSC_USER_DEF</code> .
num	gctUINT	The valid number of CSC matrix coefficients.

Returns

[vivSTATUS](#)

See also

[3.3.2 viv_dc_query_feature\(\)](#)

3 DPU APIs

3.6.7 viv_set_dither()

Description

Enables or disables the dithering feature for a display panel.

Syntax

```
vivSTATUS viv_set_dither(
    viv_display display,
    gctBOOL enable
);
```

Parameters

Parameter	Data type	Description
display	viv_display	The ID of the display panel.
enable	gctBOOL	Specifies whether to enable the dithering feature. Set this parameter to one of the following values: <ul style="list-style-type: none"> vivTRUE: Enables dithering. vivFALSE: Disables dithering.

Returns

[vivSTATUS](#)

3 DPU APIs

3.7 Display output

This section describes the APIs you can use to configure display output on panels.

Before configuring display output, call [viv_dc_query_feature\(\)](#) with `vivFEATURE_DISPLAY_COUNT` to query the number of panels supported by the display controller.

3.7.1 `viv_set_display_size()`

Description

Sets the display resolution and refresh rate of a display panel.

Syntax

```
vivSTATUS viv_set_display_size(  
    viv_display    display,  
    viv_display_size_type type  
);
```

Parameters

Parameter	Data type	Description
display	viv_display	The ID of the display panel.
type	viv_display_size_type	The display resolution and refresh rate of the display panel.

Returns

[vivSTATUS](#)

See also

[3.3.2 viv_dc_query_feature\(\)](#)

3 DPU APIs

3.7.2 viv_set_custom_display_size()

Description

Sets the custom display resolution and refresh rate of a display panel.

Syntax

```
vivSTATUS viv_set_custom_display_size(
    viv_display    display,
    gctUINT        hactive,
    gctUINT        hsync_start,
    gctUINT        hsync_end,
    gctUINT        htotal,
    gctUINT        vactive,
    gctUINT        vsync_start,
    gctUINT        vsync_end,
    gctUINT        vtotal
);
```

Parameters

Parameter	Data type	Description
display	viv_display	The ID of the display panel.
hactive	gctUINT	The active resolution in the horizontal direction.
hsync_start	gctUINT	The synchronization start of the horizontal direction, which is calculated as follows: $\text{hsync_start} = \text{hactive} + \text{h_front_porch}$ Where h_front_porch indicates the front porch of horizontal synchronization signals.
hsync_end	gctUINT	The synchronization end of horizontal direction, which is calculated as follows: $\text{hsync_end} = \text{hsync_start} + \text{h_sync_length}$ Where h_sync_length indicates the width of horizontal synchronization signals.
htotal	gctUINT	The total resolution in the horizontal direction, which is calculated as follows: $\text{htotal} = \text{hsync_end} + \text{h_back_porch}$ Where h_back_porch indicates the back porch of horizontal synchronization signals.
vactive	gctUINT	The active resolution in the vertical direction.
vsync_start	gctUINT	The synchronization start of vertical direction, which is calculated as follows: $\text{vsync_start} = \text{vactive} + \text{v_front_porch}$ Where v_front_porch indicates the front porch of vertical synchronization signals.
vsync_end	gctUINT	The synchronization end of vertical direction, which is calculated as follows: $\text{vsync_end} = \text{vsync_start} + \text{v_sync_length}$ Where v_sync_length indicates the width of vertical synchronization signals.
vtotal	gctUINT	The total resolution of vertical direction, which is calculated as follows: $\text{vtotal} = \text{vsync_end} + \text{v_back_porch}$

3 DPU APIs

Parameter	Data type	Description
		Where v_back_porch indicates the back porch of vertical synchronization signals.

Returns

[vivSTATUS](#)

See also

[3.3.2 viv_dc_query_feature\(\)](#)

3.7.3 viv_set_output()

Description

Enables or disables the output of a display panel and sets the output format.

If the Display Bus Interface (DBI) is selected as the output interface, call [viv_reset_dbi\(\)](#) to reset it to the idle state.

Syntax

```
vivSTATUS viv_set_output(
    viv_display    display,
    viv_output     *output,
    gctBOOL        enable
);
```

Parameters

Parameter	Data type	Description
display	viv_display	The ID of the display panel.
output	viv_output *	A pointer to the output configurations.
enable	gctBOOL	Specifies whether to enable the output for the display panel. Set this parameter to one of the following values: <ul style="list-style-type: none"> vivTRUE: Enables the output. Pixels are displayed on the display panel through the specified output interface. vivFALSE: Disables the output. All pixels are black. This allows a display panel to have correct timing without pixel display.

Returns

[vivSTATUS](#)

See also

[3.3.2 viv_dc_query_feature\(\)](#)

[3.7.4 viv_reset_dbi\(\)](#)

3 DPU APIs

3.7.4 viv_reset_dbi()

Description

Resets the Display Bus Interface (DBI) to the idle state. Call this API if the DBI is selected as the output interface by using `viv_set_output()`.

This API is valid only for display controllers that support DBI output. Before using this API, call `viv_dc_query_feature()` with `vivFEATURE_DBI` to check whether DBI output is supported.

Syntax

```
vivSTATUS viv_reset_dbi(  
    gctVOID  
);
```

Parameters

None.

Returns

[vivSTATUS](#)

See also

[3.3.2 viv_dc_query_feature\(\)](#)

[3.7.2 viv_set_output\(\)](#)

3.7.5 viv_set_output_dbi()

Description

Enables or disables DBI output and sets the DBI type for a display panel.

This API is valid only for display controllers that support DBI output. Before using this API, call `viv_dc_query_feature()` with `vivFEATURE_DBI` to check whether DBI output is supported.

Syntax

```
vivSTATUS viv_set_output_dbi(  
    viv_display    display,  
    viv_dbi_type   type  
);
```

Parameters

Parameter	Data type	Description
display	viv_display	The ID of the display panel.
type	viv_dbi_type	The DBI type.

Returns

[vivSTATUS](#)

3 DPU APIs

See also

[3.3.2 viv_dc_query_feature\(\)](#)

3.8 Display controller access and debugging

This section describes the APIs that you can use to commit configurations and for debugging.

3.8.1 viv_set_commit()

Description

Commits the configurations to shadow registers and triggers display panels.

Note: The shadow registers pass the configurations to the counterpart registers at the next frame. To check whether a frame is finished, use the [viv_get_vblank_count\(\)](#) API.

Syntax

```
vivSTATUS viv_set_commit(  
    gctUINT32    display_mask  
);
```

Parameters

Parameter	Data type	Description
display_mask	gctUINT32	Specifies the display panels to trigger. Set this parameter to one of the following values: <ul style="list-style-type: none">1: Triggers display0.2: Triggers display1.3: Triggers both display0 and display1.

Returns

[vivSTATUS](#)

See also

[3.8.2 viv_get_vblank_count\(\)](#)

3 DPU APIs

3.8.2 viv_get_vblank_count()

Description

Queries the number of interrupts caused. An interrupt is generated once a DC frame is finished.

You can use this API to check whether frames are finished. For details, see Section 4, [Programming with DPU APIs](#).

Syntax

```
vivSTATUS viv_get_vblank_count(
    viv_display display,
    gctUINT32 *count
);
```

Parameters

Parameter	Data type	Description
display	viv_display	The ID of the display panel.
count	gctUINT32 *	An output parameter that indicates the number of interrupts.

Returns

[vivSTATUS](#)

3.8.3 viv_set_dest()

Description

Configures the write-back feature for debugging use.

Before you call `viv_set_dest()`, make sure that the buffer to store the write-back data is configured. If you want the buffer to use system memory, call `viv_alloc_buffer()` for memory allocation.

This API is valid only if the `mem2mem` parameter in the configuration file is set to 1 and the display controller supports the write-back feature. To check whether write-back is supported, call `viv_dc_query_feature()` with `vivFEATURE_WRITEBACK`.

Syntax

```
vivSTATUS viv_set_dest(
    gctBOOL enable,
    viv_display display,
    viv_dc_buffer *buffer,
    viv_write_back_type type
    viv_display_format_type format
);
```

3 DPU APIs

Parameters

Parameter	Data type	Description
enable	gctBOOL	Specifies whether to enable the write-back feature. Set this parameter to one of the following values: <ul style="list-style-type: none"> vivTRUE: Enables write-back. vivFALSE: Disables write-back.
display	viv_display	The ID of the display panel.
buffer	viv_dc_buffer *	The buffer to store write-back data.
type	viv_write_back_type	The location inside the display controller to write back data. This parameter is valid only if the write-back feature is programmable. To check the support for the programmable write-back feature, use viv_display_query_capability() with vivDISPLAY_CAP_PROGRAM_WB .
format	viv_display_format_type	<p>(Only for DC8100) The format of the write-back data.</p> <ul style="list-style-type: none"> If type is set to vivWB_AFTER_BLENDING, select an RGB format. If type is set to vivWB_AFTER_LUT, select an RGB format or vivNV12. <p>This parameter is valid only if the write-back feature is programmable. To check the support for the programmable write-back feature, use viv_display_query_capability() with vivDISPLAY_CAP_PROGRAM_WB.</p> <p><i>Note: For hardware other than DC8100, use the format member of the buffer parameter to set the write-back data format.</i></p>

Returns

[vivSTATUS](#)

See also

[3.2.1 viv_alloc_buffer\(\)](#)

[3.3.2 viv_dc_query_feature\(\)](#)

3 DPU APIs

3.8.4 viv_set_write_back_dither()

Description

Enables or disables the write-back data dithering feature for debugging use.

This parameter is valid only if the write-back feature is programmable. To check the support for the programmable write-back feature, use `viv_display_query_capability()` with `vivDISPLAY_CAP_PROGRAM_WB`.

Syntax

```
vivSTATUS viv_set_write_back_dither(  
    viv_display display,  
    gctBOOL enable  
);
```

Parameters

Parameter	Data type	Description
display	viv_display	The ID of the display panel. Set this parameter to 0.
enable	gctBOOL	Specifies whether to enable write-back data dithering.

Returns

[vivSTATUS](#)

See also

[3.3.2 viv_dc_query_feature\(\)](#)

4 Programming with DPU APIs

4 Programming with DPU APIs

The general procedure of programming with DPU APIs is as follows:

1. Start the display controller device with the [viv_dc_init\(\)](#) API.
2. Reset the display controller with the [viv_dc_reset\(\)](#) API.
3. Query the list of features supported by the hardware with the [viv_query_chipinfo\(\)](#) and [viv_dc_query_feature\(\)](#) APIs.
4. (Optional) Allocate buffers for layers with the [viv_alloc_buffer\(\)](#) API.

Skip this step if user-reserved memory is used.

5. Program the display controller by using the APIs described in the following sections:
 - Section 3.4, [Overlay and video/graphic layers](#)
 - Section 3.5, [Background and cursor layers](#)
 - Section 3.7, [Display output](#)
 - Section 3.6, [Post-processing for display](#)
6. Configure the hardware registers and trigger panels with the [viv_set_commit\(\)](#) API.

The configurations take effect after the current frame.

7. Check whether the current frame finishes, based on the number of caused interrupts queried with the [viv_get_vblank_count\(\)](#) API.

If mem2mem in the configuration file is set to 1 and write-back is supported, you can enable the write-back feature with [viv_set_dest\(\)](#) to facilitate the memory comparison between golden and result data.

8. After the frame is finished, disable the layers and the write-back feature that are enabled in Steps 5 and 7.

This ensures that the display controller no longer has read or write requests.

For the APIs to use, see Section 3.4.2, [viv_layer_enable\(\)](#), Section 3.5.3, [viv_set_cursor\(\)](#), and Section 3.8.3, [viv_set_dest\(\)](#).

4 Programming with DPU APIs

4.1 Example 1: Displaying through DPI

This section provides an example of using the DPU API for image display through the DPI output interface. This example shows Layer 0 from (0,0) to (640,480) on the display0 panel with the output format vivD24. Layer 0 is fed with ARGB8888-formatted linear data in the size of 640x480.

For detailed description of the programming settings, see Chapter 2, [Data structures](#) and Chapter 3, [DPU APIs](#).

```
gctINT ret = 0;
gctUINT width = 640, height = 480, Bpp = 4, stride = 640*4, phyAddr = 0, vblank0 =
0,
vblank1 = 0;
void *logical = 0, *handle = 0;
viv_dc_buffer buffer = {0};
viv_dc_rect display_rect = {0};
viv_output display_output = {0};
/* open device */
ret = viv_dc_init();
if(ret)
    return ret;
/* reset DC */
viv_dc_reset();
/* select layer0 */
viv_dc_select_layer(0);
/* enable layer0 */
viv_layer_enable(vivTRUE);
/* alloc contiguous memory for the frame buffer of layer0 */
ret = viv_alloc_buffer(width*height*Bpp, &handle, &phyAddr, &logical, vivFALSE,
gcvPOOL_DEFAULT);
if(ret)
    return ret;
/* config the buffer's phyAddr/format/tilemode/bufferWidth/bufferHeight/stride to
kernel */
buffer.handle[0] = handle;
buffer.logical[0] = logical;
buffer.phyAddress[0] = phyAddr;
buffer.stride[0] = stride;
buffer.format = vivARGB8888;
buffer.tiling = vivLINEAR;
buffer.width = 640;
buffer.height = 480;
viv_layer_set(&buffer);
/* config display region on panel */
display_rect.x = 0;
display_rect.y = 0;
display_rect.w = 640;
display_rect.h = 480;
/* if display region is equal to layer0's bufferSize, don't do scale */
viv_layer_scale(&display_rect, vivFILTER_H3_V3);
/* config the start coordinates of layer0 display region */
```

4 Programming with DPU APIs

```
viv_layer_set_position(0, 0);
/* config layer's zorder number */
viv_layer_zorder(0);
/* config layer0 show on panel0 */
viv_layer_set_display(vivDISPLAY_0);
/* config panel0's resolution and timing */
viv_set_display_size(vivDISPLAY_0, vivDISPLAY_640_480_60);
/* config panel0's output type and format */
display_output.type = vivDPI;
display_output.format = vivD24;
viv_set_output(vivDISPLAY_0, &display_output, vivTRUE);
/* fill data to layer0's buffer */
memset(logical, 100, width*height*Bpp);
/* config register and trig panel0 */
viv_set_commit(0x1);
/* when vblank1 > vblank0 means one frame finished */
/* commit completes after the current frame is processed. */
viv_get_vblank_count(vivDISPLAY_0, &vblank0);
do{
    usleep(10000);
    viv_get_vblank_count(vivDISPLAY_0, &vblank1);
}while(vblank0 == vblank1);
/* we need to disable layer or cursor we have enabled before */
viv_layer_enable(vivFALSE);
/* commit again to let layer0 disabled */
viv_set_commit(0x1);
/* commit completes after the current frame is processed. */
/* new config will take effect at next frame */
viv_get_vblank_count(vivDISPLAY_0, &vblank0);
do{
    usleep(10000);
    viv_get_vblank_count(vivDISPLAY_0, &vblank1);
}while(vblank0 == vblank1);
/* free memory allocated for layer0 */
viv_free_buffer(buffer.handle[0]);
```

4 Programming with DPU APIs

4.2 Example 2: Displaying through DBI Type B

This section provides an example of using the DPU API for image display through the DBI Type B interface. This example shows Layer 0 from (0,0) to (320,480) on the display0 panel with the output format D8R8G8B8. Layer 0 is fed with ARGB8888-formatted linear data in the size of 320x480.

For detailed description of the programming settings, see Chapter 2, [Data structures](#) and Chapter 3, [DPU APIs](#).

```
gctINT ret = 0;
gctUINT width = 320, height = 480, Bpp = 4, stride = 320*4, phyAddr = 0, vblank0 =
0,
vblank1 = 0;
void *logical = 0, *handle = 0;
viv_dc_buffer buffer = {0};
viv_dc_rect display_rect = {0};
viv_output display_output = {0};
viv_dbi_type dbi_type = vivDBI_B;
/* open device */
ret = viv_dc_init();
if(ret)
    return ret;
/* reset DC */
viv_dc_reset();
/* select layer0 */
viv_dc_select_layer(0);
/* enable layer0 */
viv_layer_enable(vivTRUE);
/* alloc contiguous memory for the frame buffer of layer0 */
ret = viv_alloc_buffer(width*height*Bpp, &handle, &phyAddr, &logical, vivFALSE,
gcvPOOL_DEFAULT);
if(ret)
    return ret;
/* config the buffer's phyAddr/format/tilemode/bufferWidth/bufferHeight/stride to
kernel */
buffer.handle[0] = handle;
buffer.logical[0] = logical;
buffer.phyAddress[0] = phyAddr;
buffer.stride[0] = stride;
buffer.format = vivARGB8888;
buffer.tiling = vivLINEAR;
buffer.width = width;
buffer.height = height;
viv_layer_set(&buffer);
/* config display region on panel */
display_rect.x = 0;
display_rect.y = 0;
display_rect.w = width;
display_rect.h = height;
/* if display region is equal to layer0's bufferSize, don't do scale */
viv_layer_scale(&display_rect, vivFILTER_H3_V3);
```

4 Programming with DPU APIs

```
/* config the start coordinates of layer0 display region */
viv_layer_set_position(0, 0);
/* config layer's zorder number */
viv_layer_zorder(0);
/* config layer0 show on panel0 */
viv_layer_set_display(vivDISPLAY_0);
/* config panel0's resolution and timing */
viv_set_display_size(vivDISPLAY_0, vivDISPLAY_320_480_60);
/* config panel0's output type and format */
display_output.type = vivDBI;
display_output.format = vivD8R8G8B8;
viv_set_output(vivDISPLAY_0, &display_output, vivTRUE);
viv_reset_dbi();
viv_set_output_dbi(dbi_type);
/* fill data to layer0's buffer */
memset(logical, 100, width*height*Bpp);
/* config register and trig panel0 */
viv_set_commit(0x1);
/* when vblank1 > vblank0 means one frame finished */
/* commit completes after the current frame is processed. */
viv_get_vblank_count(vivDISPLAY_0, &vblank0);
do{
    usleep(10000);
    viv_get_vblank_count(vivDISPLAY_0, &vblank1);
}while(vblank0 == vblank1);
/* we need to disable layer or cursor we have enabled before */
viv_layer_enable(vivFALSE);
/* commit again to let layer0 disabled */
viv_set_commit(0x1);
/* commit completes after the current frame is processed. */
/* new config will take effect at next frame */
viv_get_vblank_count(vivDISPLAY_0, &vblank0);
do{
    usleep(10000);
    viv_get_vblank_count(vivDISPLAY_0, &vblank1);
}while(vblank0 == vblank1);
/* free memory allocated for layer0 */
viv_free_buffer(buffer.handle[0]);
```

Revision history

Revision history

Document revision	Date	Description of changes
**	2024-12-10	Initial release

Trademarks

All referenced product or service names and trademarks are the property of their respective owners.

Edition 2024-12-10

Published by

Infineon Technologies AG

81726 Munich, Germany

© 2024 Infineon Technologies AG.

All Rights Reserved.

Do you have a question about this document?

Email:

erratum@infineon.com

Document reference

002-40807 Rev. **

Important notice

The information given in this document shall in no event be regarded as a guarantee of conditions or characteristics ("Beschaffheitsgarantie").

With respect to any examples, hints or any typical values stated herein and/or any information regarding the application of the product, Infineon Technologies hereby disclaims any and all warranties and liabilities of any kind, including without limitation warranties of non-infringement of intellectual property rights of any third party.

In addition, any information given in this document is subject to customer's compliance with its obligations stated in this document and any applicable legal requirements, norms and standards concerning customer's products and any use of the product of Infineon Technologies in customer's applications.

The data contained in this document is exclusively intended for technically trained staff. It is the responsibility of customer's technical departments to evaluate the suitability of the product for the intended application and the completeness of the product information given in this document with respect to such application.

Warnings

Due to technical requirements products may contain dangerous substances. For information on the types in question please contact your nearest Infineon Technologies office.

Except as otherwise explicitly approved by Infineon Technologies in a written document signed by authorized representatives of Infineon Technologies, Infineon Technologies' products may not be used in any applications where a failure of the product or any consequences of the use thereof can reasonably be expected to result in personal injury.